

Introduction


The objective of this document is to give an overview about the architectural design of SalesMate +. This will enable the third party developers to develop plug-ins and custom branded software based on Salesmate + SDK. Salesmate + is a general-purpose package for managing the day-to-day activities of any shops. The idea behind the SMP architectural design is to make this application as a framework for building custom application tailored to the particular needs of any type of shops/customers. The custom application includes video rental software, Oxygen Bar Software, POS Software, Jewellery Management software etc. The architecture is flexible enough to build multilingual software tailored any language other than English. This is achieved by Customising SMP Resource DLL shipping with the SDK / package.

Major design factors


The design of the system is such that minimal effort will be required from the developer side to customize, configure and deploy the software using the SDK Supplied. Care also taken to support all the relevant industry standard Technologies like COM, Plugins, .NET etc.

SalesMate + System Architecture

Fig 2 shows the System architecture of the SalesMate + system. The main component of the system is the application itself (**SalesMatePlus.exe**). This application loads components one by one as discussed below. The components includes the SalesMatePlus.ini settings file, SMPOEM.ini file, Various add-in implemented in the particular component category specified in the SMPOEM.ini file, loading of database and default settings etc. The functionalities of the Main components in the applications are exposed through COM Automation interfaces. The developer can utilize these interfaces so as to customize the application to suit the organization needs.



How to Create and Debug Plug-ins



How to Create Custom Applications(OEM)

To customize the SalesMate + application , you need to customize the SMPOEM.ini file with your own entries. This file should be installed in the application executable folder itself along with associated files such as About box bitmap, resource DLL etc. Please note that all these entries except AppTitle and OEMAppKey are optional. Please note that SMPOEM.ini file is optional. If the SMPOEM.ini file is not present in the application folder, then the application will load the default SaleMate + settings. Once these tasks are done you need to create the installation application. We will guide you with how to create the installation setup once you have done with all the formalities regarding OEM Licensing. You need to purchase the necessary OEM License and sign OEM License agreement with KTS InfoTech.

SMPOEM.ini

[Options]
AppTitle=Your Application Title
OEMAppKey=3880036
AppVersion=3.0
AppCode=UA1
AboutMenuTitle=&About Application Title
CopyRight=Copyright © Your Company name
OEMResDLL=SalesMatePlusRes.dll
Component Category={(66DBC8C6-B4D0-48C4-988D-47D7B35E127B)}
OEMWebSite=http://www.yourwebsite.com
OEMBgColor=192192
OEMRegistryKey= Your Company name
OEMAboutBMP=OEMAbout.bmp
OEMTrialExpirationText=Trial period expired. Please register KTS SalesMate + ..
FreeVersionName=Starter Edition
PaidVersionName=Enterprise Edition
EvaluationVersionText=Evaluation Version

SalesMate + Addin Security settings format

A sample security settings format is given blow

```
<SmpPOSSecurity>
<Value>1</Value>
<SecurityVer>2</SecurityVer>
<Module>
  <Name> SmpPOS Module </Name>
  <Value>1</Value>
  <Screen>
    <Name>Access Setup</Name>
    <Value>1</Value>
    <SubScreen>
      <Name>POS</Name>
      <Value>1</Value>
    </SubScreen>
  </Screen>
</Module>
</SmpPOSSecurity>
```

The tag names has its usual default meaning and purpose. The paragraphs below will explain each tags in detail.

SmpPOSSecurity:-- The main starting tag of the SalesMate + add-in . Can be any unique tag .

Value:-- Enable or disable the whole menu. Enable -1 , disable 0.

SecurityVer:-- The Salesmate + addin security version..

Module:-- The main security add-in module name..

Name :-- The name of the module, screen or sub screen..

Screen:-- The main screen name like Access Setup, Access Transaction etc. **The screen tag cannot be nested.**

SubScreen:-- The sub screen which is the leaf node which contains the security information.

SalesMate + Addin Menu and Toolbar

Commands format

A sample format for the menu and toolbar commands is given below

```
<SmpAddin>
  <AppVer>2</AppVer>
  <AddinName> Sample SMP addin </AddinName>
  <ToobarButtonCount> 3 </ToobarButtonCount>
  <MainMenu>
    <Name>Sample SMP addin</Name>
    <SubMenu>
      <Name>My Submenu </Name>

      <ShortcutKeyIndex>1</ShortcutKeyIndex>
      <LeafMenu>
        <Name>Leafmenu 1 </Name>
        <FunctionName> SampleSmpMethod1 </FunctionName>
        <HelpString> Some status bar Help Desc</HelpString>
        <ToolTip> Tooltip Desc 1 </ToolTip>
        <ToolBarIndex> 0 </ToolBarIndex>
        <ShortCutKey> Ctrl+0 </ShortCutKey>
        <ToolBarButtonText> MyButton1</ToolBarButtonText>
        <Separator>1</Separator>
      </LeafMenu>
      <LeafMenu>
        <Name>Leafmenu 2</Name>
        <FunctionName> SampleSmpMethod2 </FunctionName>
        <HelpString> Some status bar Help Desc</HelpString>
        <ToolTip> Tooltip Desc 2 </ToolTip>
        <ToolBarIndex> 1</ToolBarIndex>
        <ShortCutKey> Ctrl+1 </ShortCutKey>
```

```

<ToolBarButtonText> MyButton2</ToolBarButtonText>
<Separator>1</Separator>
</LeafMenu>
<LeafMenu>
  <Name>Leafmenu 3</Name>
  <FunctionName> SampleSmpMethod3 </FunctionName>
  <HelpString> Some status bar Help Desc</HelpString>
  <ToolTip> Tooltip Desc 3 </ToolTip>
  <ToolBarIndex> 2</ToolBarIndex>
  <ShortCutKey> Ctrl+2</ShortCutKey>
  <ToolBarButtonText> MyButton3</ToolBarButtonText>
  <Separator>1</Separator>
</LeafMenu>
</SubMenu>
</MainMenu>
</SmpAddin>

```

The tag names has its usual default meaning and purpose. The paragraphs below will explain each tags in detail.

SmpAddin :-- The main starting tag of the SalesMate + add-in

AppVer :-- The version of the addin.

AddinName :-- The name of the add-in that should be displayed in toolbar menu and about box menu.

ToobarButtonCount :-- The toolbar button count of application.
Please set the correct toolbar button count.

MainMenu :-- The main menu tag. the menu can also be the existing File , setup as well as new user defined menu.

ShortcutKeyIndex :-- The index of the shortcut key in which we

need to place the & symbol in the menu.

SubMenu :-- The sub menu tag. The sub menu can go N level.

LeafMenu :-- The leaf menu name.

Name :-- The name of the menu (Main menu, sub menu and leaf menu)

FunctionName :-- The Addin COM Method which should be invoked when the user click on the menu or toolbar button.

HelpString :-- The string that should be displayed in the status bar when a user places the mouse cursor in the menu.

ToolTip :-- The tooltip that should be displayed in the toolbar button.

ToolBarIndex :-- The index of the toolbar button to which the menu command should be attached.

ShortCutKey :-- The default menu shortcut key assignment like **Ctrl + K**

ToolBarButtonText :-- The short text in the toolbar button.

Separator :-- The menu separator tag.

Coclass: Customer

Interface: ICustomer

[Browse members alphabetically](#)

[Browse members by category](#)

[Browse members by use](#)

ICustomer members

Properties

Name	Type	HelpString	Category	Frequency of use
GetCustomerDetails	Method	method GetCustomerDetails	General	Normal
InvokeFindCustomerDlg	Method	method InvokeFindCustomerDlg	General	Normal

[ICustomer overview](#)

ICustomer::GetCustomerDetails

method GetCustomerDetails

```
Sub GetCustomerDetails(strCustomerID As String, strFieldName As String, pvarVal)
```

Parameters

No	Name	Type	Optional	Default	Description
1	strCustomerID	String	No	-	Customer id in BSTR type
2	strFieldName	String	No	-	Field name in BSTR format
3	pvarVal	Variant	No	-	A pointer variable for retrieving the customer details in VARIANT type

Method description

Retrieve the customer details

Example code

```
CComPtr<ICustomer>m_ICustomer;
CString strCustId,strFieldName;
VARIANT Val;
BSTR bstrCusId;
HRESULT hr;

hr=m_ICustomer.CoCreateInstance(CLSID_Customer);
if(FAILED(hr))
{
    AfxMessageBox(_T("ICustomerInterface initialisation failed"))
    return FALSE;
}
m_ICustomer->GetCustomerDetails(strCustId.AllocSysString(),strFieldN
bstrCusId=Val.bstrVal;
CString strCustDetails(bstrCusId);
strFieldName+=" Field Value";
MessageBox(strCustDetails,strFieldName,MB_ICONINFORMATION | MB_OK);
```

[Back to ICustomer members](#)

(C) 1999-2001 My Company All rights reserved

ICustomer::InvokeFindCustomerDlg

method InvokeFindCustomerDlg

```
Sub InvokeFindCustomerDlg(pCustomerID As String)
```

Parameters

No	Name	Type	Optional	Default	Description
1	pCustomerID	String	No	-	Customer id in BSTR type

Method description

Invokethe FindCustomer Dialog

Example code

```
BSTR strVal;  
HRESULT hr;  
  
hr=m_ICustomer.CoCreateInstance(CLSID_Customer);  
if(FAILED(hr))  
{  
    AfxMessageBox(_T("ICustomerInterface initialisation failed"))  
    return FALSE;  
}  
m_ICustomer->InvokeFindCustomerDlg(&strVal);
```

[Back to ICustomer members](#)

Coclass: Item

Interface: IItem

[Browse members alphabetically](#)

[Browse members by category](#)

[Browse members by use](#)

IItem members

Properties

Name	Type	HelpString	Category	Frequency of use
Col	Property Get/Let	property Col	General	Normal
Content	Property Get/Let	property Content	General	Normal
ContentType	Property Get/Let	property ContentType	General	Normal
HAlign	Property Get/Let	property HAlign	General	Normal
MaxCol	Property Get/Let	property MaxCol	General	Normal
MaxRow	Property Get/Let	property MaxRow	General	Normal
Row	Property Get/Let	property Row	General	Normal

Item overview

IItem::Col

property Col

Property Get/Let Col As Long

No parameters

Property description

Get or Put the Column as long

[Back to IItem members](#)

IItem::Content

property Content

Property Get/Let Content As String

No parameters

Property description

Get or Put the content as BSTR

[Back to IItem members](#)

(C) 1999-2001 My Company All rights reserved

IItem::ContentType

property ContentType

Property Get/Let ContentType As Long

No parameters

Property description

Get or Put the content type as long

[Back to IItem members](#)

IItem::HAlign

property HAlign

Property Get/Let HAlign As Long

No parameters

Property description

Get or Put the horizontal alignment of the item as long type

[Back to IItem members](#)

IItem::MaxCol

property MaxCol

Property Get/Let MaxCol As Long

No parameters

Property description

Get or Put the maximum column as long

[Back to IItem members](#)

IItem::MaxRow

property MaxRow

Property Get/Let MaxRow As Long

No parameters

Property description

Get or Put the maximum row as long

[Back to IItem members](#)

IItem::Row

property Row

Property Get/Let Row As Long

No parameters

Property description

Get or Put the Row as long

[Back to IItem members](#)

(C) 1999-2001 My Company All rights reserved

Coclass: Reports

Interface: IReports

[Browse members alphabetically](#)

[Browse members by category](#)

[Browse members by use](#)

IReports members

Properties

Name	Type	HelpString	Category	Frequency of use
FillReport	Method	method FillReport	General	Normal
FillReportEx	Method	method FillReportEx	General	Normal
FillReportWithCaption	Method	method FillReportWithCaption	General	Normal

[IReports overview](#)

IReports::FillReport

method FillReport

```
Sub FillReport(strSQLQuery)
```

Parameters

No	Name	Type	Optional	Default	Description
1	strSQLQuery	Variant	No	-	A VARIANT value containing the SQL Query to retrieve data from database

Method description

It is used to fill the report

Example code

```
CComPtr<IReports>m_Reports;
HRESULT hr=m_Reports.CoCreateInstance(CLSID_Reports);

VARIANT varSQLQuery;
CString strSQLQuery = _T("""SELECT * FROM """+ strTableName); //strTa

varSQLQuery.vt=VT_BSTR;
varSQLQuery.bstrVal=strSQLQuery.AllocSysString();

m_Reports->FillReport(varSQLQuery);
```

[Back to IReports members](#)

IReports::FillReportEx

method FillReportEx

```
Sub FillReportEx(strQuery As String, strHeading As String,  
strAdditionalHeading As String, bShowHeader As Long, bShowFooter As  
Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	strQuery	String	No	-	A BSTR value containing the SQL Query to retrieve data from database
2	strHeading	String	No	-	A CString containing the Heading for the report
3	strAdditionalHeading	String	No	-	A BSTR value containing the Heading for the report
4	bShowHeader	Long	No	-	A boolean value used to enable or disable Header Text
5	bShowFooter	Long	No	-	A boolean value used to enable or disable Footer Text

Method description

It is used to fill the report with some additional options such as heading,additional heading, footer and header

Example code

```
CCoMPtr<IReports>m_Reports;  
HRESULT hr=m_Reports.CoCreateInstance(CLSID_Reports);  
  
BSTR bstrHeading,bstrAdditionalHeading ;  
CString strSQLQuery = _T("SELECT * FROM "+ strTableName); //strTab  
varSQLQuery.vt=VT_BSTR;  
varSQLQuery.bstrVal=strSQLQuery.AllocSysString();  
CString strHeading =_T("Some Heading");  
CString strAddHeading =_T("Some Additional Heading");  
bstrHeading=strHeading.AllocSysString();  
bstrAdditionalHeading=strAddHeading.AllocSysString();  
BOOL bShowHeader=TRUE;//(For showing header / FALSE to hide)  
BOOL bShowFooter = TRUE;//(For showing footer / FALSE to hide)
```

[Back to IReports members](#)

(C) 1999-2001 My Company All rights reserved

IReports::FillReportWithCaption

method FillReportWithCaption

```
Sub FillReportWithCaption(strSQLQuery, strCaption)
```

Parameters

No	Name	Type	Optional	Default	Description
1	strSQLQuery	Variant	No	-	A VARIANT containing the SQL Query to retrieve data from database
2	strCaption	Variant	No	-	A VARIANT containing the Caption for the report

Method description

It is used to fill the report with caption

Example code

```
CCoMPtr<IReports>m_Reports;
HRESULT hr=m_Reports.CoCreateInstance(CLSID_Reports);

CString strSQLQuery = _T("""SELECT * FROM """+ strTableName);//strTabl

VARIANT varSQLQuery;
varSQLQuery.vt=VT_BSTR;
CString strCaption=_T("Some Caption");
varCaption.bstrVal=strCaption.AllocSysString();

m_Reports->FillReportWithCaption(varSQLQuery,varCaption);
```

[Back to IReports members](#)

Coclass: TansactionEvents

Interface: ITansactionEvents

[Browse members alphabetically](#)

[Browse members by category](#)

[Browse members by use](#)

ITransactionEvents members

Properties

Name	Type	HelpString	Category	Frequency of use
OnAddTransaction	Method	method OnAddTransaction	General	Normal
OnDeleteTransaction	Method	method OnDeleteTransaction	General	Normal
OnEditTransaction	Method	method OnEditTransaction	General	Normal

[ITransactionEvents overview](#)

ITransactionEvents::OnAddTransaction

method OnAddTransaction

```
Sub OnAddTransaction(strTransactionID As String)
```

Parameters

No	Name	Type	Optional	Default	Description
1	strTransactionID	String	No	-	Transaction Id as BSTR

Method description

Event fired when adding transactions

[Back to ITransactionEvents members](#)

ITransactionEvents::OnDeleteTransaction

method OnDeleteTransaction

```
Sub OnDeleteTransaction(strTransactionID As String)
```

Parameters

No	Name	Type	Optional	Default	Description
1	strTransactionID	String	No	-	Transaction Id as BSTR

Method description

Event fired when deleting transactions

[Back to ITransactionEvents members](#)

ITransactionEvents::OnEditTransaction

method OnEditTransaction

```
Sub OnEditTransaction(strTransactionID As String)
```

Parameters

No	Name	Type	Optional	Default	Description
1	strTransactionID	String	No	-	Transaction Id as BSTR

Method description

Event fired when editing transactions

[Back to ITransactionEvents members](#)

Coclass: SalesCheckout

Interface: ISalesCheckout

[Browse members alphabetically](#)

[Browse members by category](#)

[Browse members by use](#)

ISalesCheckout members

Properties

Name	Type	HelpString	Category	Frequency of use
InvokeSalesCheckoutDlg	Method	method InvokeSalesCheckoutDlg	General	Normal

[ISalesCheckout overview](#)

ISalesCheckout::InvokeSalesCheckoutDlg

method InvokeSalesCheckoutDlg

```
Sub InvokeSalesCheckoutDlg
```

No parameters

Method description

Invoke the Sales Checkout Dialog

Example code

```
HRESULT hr;
CComPtr<ISalesCheckout>m_ISalesCheckout;

hr=m_ISalesCheckout.CoCreateInstance(CLSID_SalesCheckout);
if(FAILED(hr))
{
    AfxMessageBox(_T("ISalesCheckout Interface initialisation failed"));
    return FALSE;
}

hr=m_ISalesCheckout->InvokeSalesCheckoutDlg();
if(FAILED(hr))
{
    AfxMessageBox(_T("Invoke SalesCheckoutDlg failed"));
}
```

[Back to ISalesCheckout members](#)

Coclass: SalesCheckoutEvents

Interface: ISalesCheckoutEvents

[Browse members alphabetically](#)

[Browse members by category](#)

[Browse members by use](#)

ISalesCheckoutEvents members

Properties

Name	Type	HelpString	Category	Frequency of use
OnCheckout	Method	method OnCheckout	General	Normal

[ISalesCheckoutEvents overview](#)

ISalesCheckoutEvents::OnCheckout

method OnCheckout

```
Sub OnCheckout(strSalesTransID As String)
```

Parameters

No	Name	Type	Optional	Default	Description
1	strSalesTransID	String	No	-	

Method Description

Navigates the control of the application into the POS Terminal.

[Back to ISalesCheckoutEvents members](#)

Coclass: Transactions

Interface: ITransactions

[Browse members alphabetically](#)

[Browse members by category](#)

[Browse members by use](#)

ITransactions members

Properties

Name	Type	HelpString	Category	Frequency of use
InvokeAddMiscExpenseDlg	Method	method InvokeAddMiscExpenseDlg	General	Normal
InvokeAddMiscIncomeDlg	Method	method InvokeAddMiscIncomeDlg	General	Normal
InvokeAddTransactionDlg	Method	method InvokeAddTransactionDlg	General	Normal
InvokeCancelTransactionDlg	Method	method InvokeCancelTransactionDlg	General	Normal
InvokeEditMiscExpenseDlg	Method	method InvokeEditMiscExpenseDlg	General	Normal
InvokeEditMiscIncomeDlg	Method	method InvokeEditMiscIncomeDlg	General	Normal
InvokeEditTransactionDlg	Method	method InvokeEditTransactionDlg	General	Normal

ITransactions overview

ITransactions::InvokeAddMiscExpenseDlg

method InvokeAddMiscExpenseDlg

```
Sub InvokeAddMiscExpenseDlg
```

No parameters

Method description

It is used to invoke the Add miscellaneous Expense DIalog

Example code

```
CComPtr<ITransactions>m_Transaction;  
HRESULT hr=m_Transaction.CoCreateInstance(CLSID_Transactions);  
if(FAILED(hr))  
{  
    AfxMessageBox(_T("Transaction Settings Failed"));  
    return FALSE;  
}  
if(E_FAIL==m_Transaction->InvokeAddMiscExpenseDlg())  
{  
    AfxMessageBox(_T("Access denied"));  
}
```

[Back to ITransactions members](#)

ITransactions::InvokeAddMiscIncomeDlg

method InvokeAddMiscIncomeDlg

```
Sub InvokeAddMiscIncomeDlg
```

No parameters

Method description

It is used to invoke the Add miscellaneous Income DIalog

Example code

```
CComPtr<ITransactions>m_Transaction;  
HRESULT hr=m_Transaction.CoCreateInstance(CLSID_Transactions);  
if(FAILED(hr))  
{  
    AfxMessageBox(_T("Transaction Settings Failed"));  
    return FALSE;  
}  
if(E_FAIL==m_Transaction->InvokeAddMiscIncomeDlg())  
{  
    AfxMessageBox(_T("Access denied"));  
}
```

[Back to ITransactions members](#)

ITransactions::InvokeAddTransactionDlg

method InvokeAddTransactionDlg

```
Sub InvokeAddTransactionDlg
```

No parameters

Method description

It is used to invoke the Add Transaction Dialog

Example code

```
CComPtr<ITransactions>m_Transaction;  
HRESULT hr=m_Transaction.CoCreateInstance(CLSID_Transactions);  
if(FAILED(hr))  
{  
    AfxMessageBox(_T("Transaction Settings Failed"));  
    return FALSE;  
}  
if(E_FAIL==m_Transaction->InvokeAddTransactionDlg())  
{  
    AfxMessageBox(_T("Access denied"));  
}
```

[Back to ITransactions members](#)

ITransactions::InvokeCancelTransactionDlg

method InvokeCancelTransactionDlg

```
Sub InvokeCancelTransactionDlg
```

No parameters

Method description

It is used to invoke the Cancel Transaction Dialog

Example code

```
CComPtr<ITransactions>m_Transaction;  
HRESULT hr=m_Transaction.CoCreateInstance(CLSID_Transactions);  
if(FAILED(hr))  
{  
    AfxMessageBox(_T("Transaction Settings Failed"));  
    return FALSE;  
}  
if(E_FAIL==m_Transaction->InvokeCancelTransactionDlg())  
{  
    AfxMessageBox(_T("Access denied"));  
}
```

[Back to ITransactions members](#)

ITransactions::InvokeEditMiscExpenseDlg

method InvokeEditMiscExpenseDlg

```
Sub InvokeEditMiscExpenseDlg
```

No parameters

Method description

It is used to invoke the Edit miscellaneous Expense Dialog

Example code

```
CComPtr<ITransactions>m_Transaction;  
HRESULT hr=m_Transaction.CoCreateInstance(CLSID_Transactions);  
if(FAILED(hr))  
{  
    AfxMessageBox(_T("Transaction Settings Failed"));  
    return FALSE;  
}  
if(E_FAIL==m_Transaction->InvokeEditTransactionDlg())  
{  
    AfxMessageBox(_T("Access denied"));  
}
```

[Back to ITransactions members](#)

ITransactions::InvokeEditMiscIncomeDlg

method InvokeEditMiscIncomeDlg

```
Sub InvokeEditMiscIncomeDlg
```

No parameters

Method description

It is used to invoke the Edit miscellaneous Income Dialog

Example code

```
CComPtr<ITransactions>m_Transaction;  
HRESULT hr=m_Transaction.CoCreateInstance(CLSID_Transactions);  
if(FAILED(hr))  
{  
    AfxMessageBox(_T("Transaction Settings Failed"));  
    return FALSE;  
}  
if(E_FAIL==m_Transaction->InvokeEditMiscExpenseDlg())  
{  
    AfxMessageBox(_T("Access denied"));  
}
```

[Back to ITransactions members](#)

ITransactions::InvokeEditTransactionDlg

method InvokeEditTransactionDlg

```
Sub InvokeEditTransactionDlg
```

No parameters

Method description

It is used to invoke the Edit Transaction Dialog

Example code

```
CComPtr<ITransactions>m_Transaction;  
HRESULT hr=m_Transaction.CoCreateInstance(CLSID_Transactions);  
if(FAILED(hr))  
{  
    AfxMessageBox(_T("Transaction Settings Failed"));  
    return FALSE;  
}  
if(E_FAIL==m_Transaction->InvokeEditTransactionDlg())  
{  
    AfxMessageBox(_T("Access denied"));  
}
```

[Back to ITransactions members](#)

Coclass: Settings

Interface: ISettings

[Browse members alphabetically](#)

[Browse members by category](#)

[Browse members by use](#)

ISettings members

Properties

Name	Type	HelpString	Category	Frequency of use
AutomaticBackup	Property Get	property AutomaticBackup	General	Normal
AutomaticCompact	Property Get	property AutomaticCompact	General	Normal
CompactDatabase	Method	method CompactDatabase	General	Normal
DateFormat	Property Get	property DateFormat	General	Normal
DefaultMembershipFee	Property Get	property DefaultMembershipFee	General	Normal
DefaultSecurityDeposit	Property Get	property DefaultSecurityDeposit	General	Normal
LaunchOnStartup	Property Get	property LaunchOnStartup	General	Normal
NoOfDisplayRecords	Property Get	property NoOfDisplayRecords	General	Normal
OverrideExDataOnAB	Property Get	property OverrideExDataOnAB	General	Normal
PaymentMethod	Property Get/Let	property PaymentMethod	General	Normal
PictureFolder	Property Get	property PictureFolder	General	Normal
UseEnterKey	Property Get	property UseEnterKey	General	Normal

[ISettings overview](#)

ISettings::AutomaticBackup

property AutomaticBackup

Property Get AutomaticBackup As Long

No parameters

Property description

Used to check whether Automatic backup is enabled or not

Example code

```
CComPtr<ISettings>m_ISettings;  
HRESULT hr = m_ISettings.CoCreateInstance(CLSID_Settings);
```

[Back to ISettings members](#)

ISettings::AutomaticCompact

property AutomaticCompact

Property Get AutomaticCompact As Long

No parameters

Property description

Used to check whether Automatic backup is enabled or not

Example code

```
CComPtr<ISettings>m_ISettings;  
HRESULT hr = m_ISettings.CoCreateInstance(CLSID_Settings);
```

[Back to ISettings members](#)

ISettings::CompactDatabase

method CompactDatabase

```
Sub CompactDatabase
```

No parameters

Method description

Used to compact Database

Example code

```
CComPtr<ISettings>m_ISettings;  
HRESULT hr = m_ISettings.CoCreateInstance(CLSID_Settings);
```

[Back to ISettings members](#)

ISettings::DateFormat

property DateFormat

```
Property Get DateFormat As String
```

No parameters

Property description

Used to get the date format

Example code

```
CComPtr<ISettings>m_ISettings;  
HRESULT hr = m_ISettings.CoCreateInstance(CLSID_Settings);  
m_ISettings->get_DateFormat(&bstr.DateFormat);
```

[Back to ISettings members](#)

ISettings::DefaultMembershipFee

property DefaultMembershipFee

```
Property Get DefaultMembershipFee As Double
```

No parameters

Property description

Used to get the default membership fee

Example code

```
CComPtr<ISettings>m_ISettings;  
HRESULT hr = m_ISettings.CoCreateInstance(CLSID_Settings);  
m_ISettings->get_DefaultMembershipFee(&d_double);
```

[Back to ISettings members](#)

ISettings::DefaultSecurityDeposit

property DefaultSecurityDeposit

```
Property Get DefaultSecurityDeposit As Double
```

No parameters

Property description

Used to get default security deposit

Example code

```
CComPtr<ISettings>m_ISettings;  
HRESULT hr = m_ISettings.CoCreateInstance(CLSID_Settings);  
m_ISettings->get_DefaultSecurityDeposit(&d_double);
```

[Back to ISettings members](#)

ISettings::LaunchOnStartup

property LaunchOnStartup

Property Get LaunchOnStartup As Long

No parameters

Property description

Used to check whether launch on start up is enabled or not

Example code

```
CComPtr<ISettings>m_ISettings;  
HRESULT hr = m_ISettings.CoCreateInstance(CLSID_Settings);  
m_ISettings->get_LaunchOnStartup(&bval);
```

[Back to ISettings members](#)

ISettings::NoOfDisplayRecords

property NoOfDisplayRecords

```
Property Get NoOfDisplayRecords As Long
```

No parameters

Property description

Used to get the number of display records

Example code

```
CComPtr<ISettings>m_ISettings;  
HRESULT hr = m_ISettings.CoCreateInstance(CLSID_Settings);  
m_ISettings->get_NoOfDisplayRecords(&bval);
```

[Back to ISettings members](#)

ISettings::OverrideExDataOnAB

property OverrideExDataOnAB

Property Get OverrideExDataOnAB As Long

No parameters

Example code

```
CCoMPtr<ISettings>m_ISettings;  
HRESULT hr = m_ISettings.CoCreateInstance(CLSID_Settings);  
m_ISettings->get_OverrideExDataOnAB(&bval);
```

[Back to ISettings members](#)

ISettings::PaymentMethod

property PaymentMethod

Property Get/Let PaymentMethod As String

No parameters

Property description

Used to get the payment method

Example code

```
CComPtr<ISettings>m_ISettings;  
HRESULT hr = m_ISettings.CoCreateInstance(CLSID_Settings);  
m_ISettings->get_PaymentMethod(&bstr_PaymentMethod);
```

[Back to ISettings members](#)

ISettings::PictureFolder

property PictureFolder

```
Property Get PictureFolder As String
```

No parameters

Property description

Used to get the Picture folder path

Example code

```
CComPtr<ISettings>m_ISettings;  
HRESULT hr = m_ISettings.CoCreateInstance(CLSID_Settings);  
m_ISettings->get_PictureFolder(&bstr_PictureFolder);
```

[Back to ISettings members](#)

ISettings::UseEnterKey

property UseEnterKey

Property Get UseEnterKey As Long

No parameters

Property description

Use to check whether Enter key navigation is enabled or not

Example code

```
CComPtr<ISettings>m_ISettings;  
HRESULT hr = m_ISettings.CoCreateInstance(CLSID_Settings);  
m_ISettings->get_UseEnterKey(&bval);
```

[Back to ISettings members](#)

Coclass: Security

Interface: ISecurity

[Browse members alphabetically](#)

[Browse members by category](#)

[Browse members by use](#)

ISecurity members

Properties

Name	Type	HelpString	Category	Frequency of use
AccessCustomerMenu	Property Get	property AccessCustomerMenu	General	Normal
AccessSalesMenu	Property Get	property AccessSalesMenu	General	Normal
AccessSetup	Property Get	property AccessSetup	General	Normal
AccessTransactionMenu	Property Get	property AccessTransactionMenu	General	Normal
CurrentLoginUser	Property Get	property CurrentLoginUser	General	Normal
CurrentUserRights	Property Get	property CurrentUserRights	General	Normal
DatabaseRight	Property Get	property DatabaseRight	General	Normal
 GetUserRightsInfo	Method	method GetUserRightsInfo	General	Normal
PrintReports	Property Get	property PrintReports	General	Normal
UpdateShopBalance	Property Get	property UpdateShopBalance	General	Normal
UserRightInfo	Property Get	property UserRightInfo	General	Normal
ViewReports	Property Get	property ViewReports	General	Normal

[ISecurity overview](#)

ISecurity::AccessCustomerMenu

property AccessCustomerMenu

Property Get AccessCustomerMenu As Long

No parameters

Property description

Used to check whether the user have Access to customer menu

Example code

```
CComPtr<ISecurity>m_ISecurity;  
HRESULT hr = m_ISecurity.CoCreateInstance(CLSID_Security);  
HRESULT hr=m_ISecurity->get_AccessCustomerMenu(&bval);
```

[Back to ISecurity members](#)

ISecurity::AccessSalesMenu

property AccessSalesMenu

Property Get AccessSalesMenu As Long

No parameters

Property description

Used to check whether the user have Access to Sales menu

Example code

```
CComPtr<ISecurity>m_ISecurity;  
HRESULT hr = m_ISecurity.CoCreateInstance(CLSID_Security);  
HRESULT hr=m_ISecurity->get_AccessSalesMenu(&bval);
```

[Back to ISecurity members](#)

ISecurity::AccessSetup

property AccessSetup

Property Get AccessSetup As Long

No parameters

Property description

Used to check whether the user have Access to Setup menu

Example code

```
CCoMPtr<ISecurity>m_ISecurity;  
HRESULT hr = m_ISecurity.CoCreateInstance(CLSID_Security);  
HRESULT hr=m_ISecurity->get_AccessSetup(&bval);
```

[Back to ISecurity members](#)

ISecurity::AccessTransactionMenu

property AccessTransactionMenu

```
Property Get AccessTransactionMenu As Long
```

No parameters

Property description

Used to check whether the user have Access to Transaction menu

Example code

```
CComPtr<ISecurity>m_ISecurity;  
HRESULT hr = m_ISecurity.CoCreateInstance(CLSID_Security);  
HRESULT hr=m_ISecurity->get_AccessTransactionMenu(&bval);
```

[Back to ISecurity members](#)

ISecurity::CurrentLoginUser

property CurrentLoginUser

```
Property Get CurrentLoginUser As String
```

No parameters

Property description

Used to get the current user

Example code

```
CComPtr<ISecurity>m_ISecurity;  
HRESULT hr = m_ISecurity.CoCreateInstance(CLSID_Security);  
m_ISecurity->get_CurrentLoginUser(&bstr_user);
```

[Back to ISecurity members](#)

ISecurity::CurrentUserRights

property CurrentUserRights

```
Property Get CurrentUserRights As String
```

No parameters

Property description

Used to retrieve the current user rights

Example code

```
CComPtr<ISecurity>m_ISecurity;  
HRESULT hr = m_ISecurity.CoCreateInstance(CLSID_Security);  
m_ISecurity->get_CurrentUserRights(&bstr_user);
```

[Back to ISecurity members](#)

ISecurity::DatabaseRight

property DatabaseRight

```
Property Get DatabaseRight As Long
```

No parameters

Property description

Used to retrieve the current user database rights

Example code

```
CComPtr<ISecurity>m_ISecurity;  
HRESULT hr = m_ISecurity.CoCreateInstance(CLSID_Security);  
HRESULT hr=m_ISecurity->get_DatabaseRight(&bval);
```

[Back to ISecurity members](#)

ISecurity:: GetUserRightsInfo

method GetUserRightsInfo

```
Sub GetUserRightsInfo(strUserID As String, pStrUserSecurityData As String)
```

Parameters

No	Name	Type	Optional	Default	Description
1	strUserID	String	No	-	BSTR variable to hold userid
2	pStrUserSecurityData	String	No	-	BSTR pointer variable to hold the rights

Method description

Used to retrieve view reports rights information

Example code

```
CComPtr<ISecurity>m_ISecurity;  
HRESULT hr = m_ISecurity.CoCreateInstance(CLSID_Security);  
HRESULT hr=m_ISecurity-> GetUserRightsInfo(bstr_username,&bstr_securi
```

[Back to ISecurity members](#)

ISecurity::PrintReports

property PrintReports

Property Get PrintReports As Long

No parameters

Property description

Used to check whether the user have Print report rights

Example code

```
CComPtr<ISecurity>m_ISecurity;  
HRESULT hr = m_ISecurity.CoCreateInstance(CLSID_Security);  
HRESULT hr=m_ISecurity->get_PrintReports(&bval);
```

[Back to ISecurity members](#)

ISecurity::UserRightInfo

property UserRightInfo

```
Property Get UserRightInfo(strXMLModuleName As String,  
strModuleSection As String, strLeafSecurityNodeName As String) As  
Long
```

Parameters

No	Name	Type	Optional	Default	Description
1	strXMLModuleName	String	No	-	BSTR variable to give module name
2	strModuleSection	String	No	-	BSTR variable to give module section
3	strLeafSecurityNodeName	String	No	-	BSTR variable to give security node name

Property description

Used to retrieve view reports rights information

Example code

```
CCoMPtr<ISecurity>m_ISecurity;  
HRESULT hr = m_ISecurity.CoCreateInstance(CLSID_Security);  
HRESULT hr = m_ISecurity->get_UserRightInfo(str_XMLModuleName, bstr
```

[Back to ISecurity members](#)

ISecurity::UpdateShopBalance

property UpdateShopBalance

Property Get UpdateShopBalance As Double

No parameters

Property description

Used to retrive the shope balance

Example code

```
CCComPtr<ISecurity>m_ISecurity;  
HRESULT hr = m_ISecurity.CoCreateInstance(CLSID_Security);  
m_ISecurity->get_UpdateShopBalance(&d_double);
```

[Back to ISecurity members](#)

ISecurity::ViewReports

property ViewReports

Property Get ViewReports As Long

No parameters

Property description

Used to retrive view reports rights

Example code

```
CComPtr<ISecurity>m_ISecurity;  
HRESULT hr = m_ISecurity.CoCreateInstance(CLSID_Security);  
HRESULT hr=m_ISecurity->get_ViewReports(&bval);
```

[Back to ISecurity members](#)

Coclass: Database

Interface: IDatabase

[Browse members alphabetically](#)

[Browse members by category](#)

[Browse members by use](#)

IDatabase members

Properties

Name	Type	HelpString	Category	Frequency of use
ConnectionInterface	Property Get	property ConnectionInterface	General	Normal
DBPath	Property Get	property DBPath	General	Normal
ExecuteQuery	Method	method ExecuteQuery	General	Normal
ExecuteQueryEx	Method	method ExecuteQueryEx	General	Normal
IsMSAccess	Property Get	property IsMSAccess	General	Normal

[IDatabase overview](#)

IDatabase::ConnectionInterface

property ConnectionInterface

Property Get ConnectionInterface As Variant

No parameters

[Back to IDatabase members](#)

(C) 1999-2001 My Company All rights reserved

IDatabase::DBPath

property DBPath

Property Get DBPath As String

No parameters

[Back to IDatabase members](#)

(C) 1999-2001 My Company All rights reserved

IDatabase::ExecuteQuery

method ExecuteQuery

```
Sub ExecuteQuery(strQuery As String, pQueryResult)
```

Parameters

No	Name	Type	Optional	Default	Description
1	strQuery	String	No	-	
2	pQueryResult	Variant	No	-	

[Back to IDatabase members](#)

IDatabase::ExecuteQueryEx

method ExecuteQueryEx

```
Sub ExecuteQueryEx(strQuery As String, pQueryResult)
```

Parameters

No	Name	Type	Optional	Default	Description
1	strQuery	String	No	-	
2	pQueryResult	Variant	No	-	

[Back to IDatabase members](#)

IDatabase::IsMSAccess

property IsMSAccess

Property Get IsMSAccess As Long

No parameters

[Back to IDatabase members](#)

(C) 1999-2001 My Company All rights reserved

Coclass: Grid

Interface: IGrid

[Browse members alphabetically](#)

[Browse members by category](#)

[Browse members by use](#)

IGrid members

Properties

Name	Type	HelpString	Category	Frequency of use
CellColour	Property Get/Let	property CellColour	General	Normal
CellFont	Property Get/Let	property CellFont	General	Normal
CellFontSize	Property Get/Let	property CellFontSize	General	Normal
CellFontType	Property Get/Let	property CellFontType	General	Normal
CellText	Property Get/Let	property CellText	General	Normal
CellTextColour	Property Get/Let	property CellTextColour	General	Normal
ColumnWidth	Property Get/Let	property ColumnWidth	General	Normal
DeleteColumn	Method	method DeleteColumn	General	Normal
DeleteRow	Method	method DeleteRow	General	Normal
HorizontalGridLine	Property Get/Let	property HorizontalGridLine	General	Normal
InsertColumn	Method	method InsertColumn	General	Normal
InsertRow	Method	method InsertRow	General	Normal
MergeCells	Method	method MergeCells	General	Normal
NoOfColumns	Property Get/Let	property NoOfColumns	General	Normal
NoOfFixedColumns	Property Get/Let	property NoOfFixedColumns	General	Normal
NoOfFixedRows	Property Get/Let	property NoOfFixedRows	General	Normal
NoOfRows	Property Get/Let	property NoOfRows	General	Normal
PrintContents	Method	method PrintContents	General	Normal
ReadOnly	Property Get/Let	property ReadOnly	General	Normal
ResetGrid	Method	method ResetGrid	General	Normal
RowHeight	Property Get/Let	property RowHeight	General	Normal
UnmergeCells	Method	method UnmergeCells	General	Normal
VerticalGridLine	Property Get/Let	property VerticalGridLine	General	Normal
WindowHandle	Property Get	property WindowHandle	General	Normal

[IGrid overview](#)

IGrid::CellColour

property CellColour

Property Get/Let CellColour(lRow As Long, lCol As Long) As Long

Parameters

No	Name	Type	Optional	Default	Description
1	lRow	Long	No	-	
2	lCol	Long	No	-	

[Back to IGrid members](#)

IGrid::CellFont

property CellFont

Property Get/Let CellFont(lRow As Long, lCol As Long) As Long

Parameters

No	Name	Type	Optional	Default	Description
1	lRow	Long	No	-	
2	lCol	Long	No	-	

[Back to IGrid members](#)

IGrid::CellFontSize

property CellFontSize

Property Get/Let CellFontSize(lRow As Long, lCol As Long) As Long

Parameters

No	Name	Type	Optional	Default	Description
1	lRow	Long	No	-	
2	lCol	Long	No	-	

[Back to IGrid members](#)

IGrid::CellFontType

property CellFontType

Property Get/Let CellFontType(lRow As Long, lCol As Long) As String

Parameters

No	Name	Type	Optional	Default	Description
1	lRow	Long	No	-	
2	lCol	Long	No	-	

[Back to IGrid members](#)

IGrid::CellText

property CellText

```
Property Get/Let CellText(lRow As Long, lCol As Long) As String
```

Parameters

No	Name	Type	Optional	Default	Description
1	lRow	Long	No	-	
2	lCol	Long	No	-	

[Back to IGrid members](#)

IGrid::CellTextColour

property CellTextColour

```
Property Get/Let CellTextColour(lRow As Long, lCol As Long) As Long
```

Parameters

No	Name	Type	Optional	Default	Description
1	lRow	Long	No	-	
2	lCol	Long	No	-	

[Back to IGrid members](#)

IGrid::ColumnWidth

property ColumnWidth

Property Get/Let ColumnWidth(lCol As Long) As Long

Parameters

No	Name	Type	Optional	Default	Description
1	lCol	Long	No	-	

[Back to IGrid members](#)

IGrid::DeleteColumn

method DeleteColumn

```
Sub DeleteColumn(lCol As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	lCol	Long	No	-	

[Back to IGrid members](#)

IGrid::DeleteRow

method DeleteRow

```
Sub DeleteRow(lRow As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	lRow	Long	No	-	

[Back to IGrid members](#)

IGrid::HorizontdalGridLine

property HorizontdalGridLine

Property Get/Let HorizontdalGridLine As Long

No parameters

[Back to IGrid members](#)

(C) 1999-2001 My Company All rights reserved

IGrid::InsertColumn

method InsertColumn

```
Sub InsertColumn(lColumn As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	lColumn	Long	No	-	

[Back to IGrid members](#)

IGrid::InsertRow

method InsertRow

```
Sub InsertRow(lRow As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	lRow	Long	No	-	

[Back to IGrid members](#)

IGrid::MergeCells

method MergeCells

```
Sub MergeCells(lStartRow As Long, lStartCol As Long, lEndRow As  
Long, lEndCol As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	lStartRow	Long	No	-	
2	lStartCol	Long	No	-	
3	lEndRow	Long	No	-	
4	lEndCol	Long	No	-	

[Back to IGrid members](#)

IGrid::NoOfColumns

property NoOfColumns

Property Get/Let NoOfColumns As Long

No parameters

[Back to IGrid members](#)

(C) 1999-2001 My Company All rights reserved

IGrid::NoOfFixedColumns

property NoOfFixedColumns

Property Get/Let NoOfFixedColumns As Long

No parameters

[Back to IGrid members](#)

(C) 1999-2001 My Company All rights reserved

IGrid::NoOfFixedRows

property NoOfFixedRows

Property Get/Let NoOfFixedRows As Long

No parameters

[Back to IGrid members](#)

(C) 1999-2001 My Company All rights reserved

IGrid::NoOfRows

property NoOfRows

Property Get/Let NoOfRows As Long

No parameters

[Back to IGrid members](#)

(C) 1999-2001 My Company All rights reserved

IGrid::PrintContents

method PrintContents

```
Sub PrintContents(lContentType As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	lContentType	Long	No	-	

[Back to IGrid members](#)

IGrid::ReadOnly

property ReadOnly

Property Get/Let ReadOnly As Long

No parameters

[Back to IGrid members](#)

(C) 1999-2001 My Company All rights reserved

IGrid::ResetGrid

method ResetGrid

```
Sub ResetGrid
```

No parameters

[Back to IGrid members](#)

IGrid::RowHeight

property RowHeight

Property Get/Let RowHeight(lRow As Long) As Long

Parameters

No	Name	Type	Optional	Default	Description
1	lRow	Long	No	-	

[Back to IGrid members](#)

IGrid::UnmergeCells

method UnmergeCells

```
Sub UnmergeCells(lStartRow As Long, lStartCol As Long, lEndRow As  
Long, lEndCol As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	lStartRow	Long	No	-	
2	lStartCol	Long	No	-	
3	lEndRow	Long	No	-	
4	lEndCol	Long	No	-	

[Back to IGrid members](#)

IGrid::VerticalGridLine

property VerticalGridLine

Property Get/Let VerticalGridLine As Long

No parameters

[Back to IGrid members](#)

(C) 1999-2001 My Company All rights reserved

IGrid::WindowHandle

property WindowHandle

Property Get WindowHandle As Variant

No parameters

[Back to IGrid members](#)

(C) 1999-2001 My Company All rights reserved

Coclass: SmpSettingsEx

ISmpSettingsEx members

Properties

Name	Type	HelpString	Category	Frequency of use
ReloadAllApplicationSettings	Method	method ReloadAllApplicationSettings	General	Normal
ReloadAllDefaultSettings	Method	method ReloadAllDefaultSettings	General	Normal
ReloadAllLocalSettings	Method	method ReloadAllLocalSettings	General	Normal

[ISmpSettingsEx overview](#)

ISmpSettingsEx::ReloadAllApplicationSettings

method ReloadAllApplicationSettings

```
Sub ReloadAllApplicationSettings
```

Parameters

No parameters

Method Description

This method is used to reload both local and default application settings.

[Back to ISmpSettingsEx members](#)

ISmpSettingsEx::ReloadAllDefaultSettings

method ReloadAllDefaultSettings

```
Sub ReloadAllDefaultSettings
```

Parameters

No parameters

Method Description

This method is used to reload the default application settings.

[Back to ISmpSettingsEx members](#)

ISmpSettingsEx::ReloadAllLocalSettings

method ReloadAllLocalSettings

```
Sub ReloadAllLocalSettings
```

No parameters

Parameters

No parameters

Method Description

This method is used to reload the local application settings.

[Back to ISmpSettingsEx members](#)

Coclass: SmpOEMEvents

Interface: ISmpOEMEvents

[Browse members alphabetically](#)

[Browse members by category](#)

[Browse members by use](#)

ISmpOEMEvents members

Properties

Name	Type	HelpString	Category	Frequency of use
InvokeCustomAccountsMenuDlg	Method	method InvokeCustomAccountsMenuDlg	General	Normal
InvokeCustomCustomerMenuDlg	Method	method InvokeCustomCustomerMenuDlg	General	Normal
InvokeCustomFileMenuDlg	Method	method InvokeCustomFileMenuDlg	General	Normal
InvokeCustomHelpMenuDlg	Method	method InvokeCustomHelpMenuDlg	General	Normal
InvokeCustomReportMenuDlg	Method	method InvokeCustomReportMenuDlg	General	Normal
InvokeCustomSalesMenuDlg	Method	method InvokeCustomSalesMenuDlg	General	Normal
InvokeCustomSetupMenuDlg	Method	method InvokeCustomSetupMenuDlg	General	Normal
InvokeCustomTransactionMenuDlg	Method	method InvokeCustomTransactionMenuDlg	General	Normal
InvokeCustomViewMenu	Method	method InvokeCustomViewMenu	General	Normal

[ISmpOEMEvents overview](#)

ISmpOEMEvents::InvokeCustomAccountsMenuDlg

method InvokeCustomAccountsMenuDlg

```
Sub InvokeCustomAccountsMenuDlg(iMenuType As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	iMenuType	Long	No	-	iMenuType in Long type

Method description

Invoke the Custom Accounts Menu dialog

Example code

```
CComPtr<ISmpOEM> SmpOEM;  
  
CString strAccountMenuCheckBox="True" ;  
if(strAccountMenuCheckBox == "True")  
{  
SmpOEM->put_InvokeCustomAccountsDlg(ID_ACCOUNTS_ACCEPTPAYMENT, TRUE);  
}  
else  
{  
SmpOEM->put_InvokeCustomAccountsDlg(ID_ACCOUNTS_ACCEPTPAYMENT, FALSE);  
}
```

[Back to ISmpOEMEvents members](#)

ISmpOEMEvents::InvokeCustomCustomerMenuDlg

method InvokeCustomCustomerMenuDlg

```
Sub InvokeCustomCustomerMenuDlg(iMenuType As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	iMenuType	Long	No	-	iMenuType in Long type

Method description

Invoke the Custom Customer Menu dialog

Example code

```
CCoMPtr<ISmpOEM> SmpOEM;  
  
CString strCustomerMenuCheckBox="True" ;  
if(strCustomerMenuCheckBox == "True")  
{  
SmpOEM->put_InvokeCustomCustomerDlg(ID_CUSTMER_ADD_CUSTOMER, TRUE);  
}  
else  
{  
SmpOEM->put_InvokeCustomCustomerDlg(ID_CUSTMER_ADD_CUSTOMER, FALSE);  
}
```

[Back to ISmpOEMEvents members](#)

ISmpOEMEvents::InvokeCustomFileDialog

method InvokeCustomFileDialog

```
Sub InvokeCustomFileDialog(iMenuType As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	iMenuType	Long	No	-	iMenuType in Long type

Method description

Invoke the Custom File Menu dialog

Example code

```
CCoMPtr<ISmpOEM> SmpOEM;  
  
CString strFileMenuCheckBox="True";  
if(strFileMenuCheckBox == "True")  
{  
SmpOEM->put_InvokeCustomFileDialog(ID_FILE_BACKUPDATABASE , TRUE);  
}  
else  
{  
SmpOEM->put_InvokeCustomFileDialog(ID_FILE_BACKUPDATABASE , FALSE);  
}
```

[Back to ISmpOEMEvents members](#)

ISmpOEMEvents::InvokeCustomHelpMenuDlg

method InvokeCustomHelpMenuDlg

```
Sub InvokeCustomHelpMenuDlg(iHelpMenuType As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	iHelpMenuType	Long	No	-	iHelpMenuType in Long type

Method description

Invoke the Custom Help Menu dialog

Example code

```
CCoMPtr<ISmpOEM> SmpOEM;  
  
CString strHelpMenuCheckBox="True";  
if(strHelpMenuCheckBox == "True")  
{  
SmpOEM->put_InvokeCustomHelpDlg(ID_HELP_REGISTER , TRUE);  
}  
else  
{  
SmpOEM->put_InvokeCustomHelpDlg(ID_HELP_REGISTER , FALSE);  
}
```

[Back to ISmpOEMEvents members](#)

ISmpOEMEvents::InvokeCustomReportMenuDlg

method InvokeCustomReportMenuDlg

```
Sub InvokeCustomReportMenuDlg(iDlgType As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	iDlgType	Long	No	-	iDlgType in Long type

Method description

Invoke the Custom Report Menu dialog

Example code

```
CComPtr<ISmpOEM> SmpOEM;  
  
CString strReportMenuCheckBox="True" ;  
if(strReportMenuCheckBox == "True")  
{  
SmpOEM->put_InvokeCustomreportsDlg(ID_REPORTS_DAILYREPORTS , TRUE);  
}  
else  
{  
SmpOEM->put_InvokeCustomreportsDlg(ID_REPORTS_DAILYREPORTS , FALSE);  
}
```

[Back to ISmpOEMEvents members](#)

ISmpOEMEvents::InvokeCustomSalesMenuDlg

method InvokeCustomSalesMenuDlg

```
Sub InvokeCustomSalesMenuDlg(iDialogType As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	iDialogType	Long	No	-	iDialogType in Long type

Method description

Invoke the Custom Sales Menu dialog

Example code

```
CComPtr<ISmpOEM> SmpOEM;  
  
CString strSalesMenuCheckBox="True" ;  
if(strSalesMenuCheckBox == "True")  
{  
SmpOEM->put_InvokeCustomSalesDlg(ID_SALES_ADD_NEW_STOCK_ITEM , TRUE);  
}  
else  
{  
SmpOEM->put_InvokeCustomSalesDlg(ID_SALES_ADD_NEW_STOCK_ITEM , FALSE);  
}
```

[Back to ISmpOEMEvents members](#)

ISmpOEMEvents::InvokeCustomSetupMenuDlg

method InvokeCustomSetupMenuDlg

```
Sub InvokeCustomSetupMenuDlg(iDialogType As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	iDialogType	Long	No	-	iDialogType in Long type

Method description

Invoke the Custom Setup Menu dialog

Example code

```
CComPtr<ISmpOEM> SmpOEM;  
  
CString strSetupMenuCheckBox="True" ;  
if(strSetupMenuCheckBox == "True")  
{  
SmpOEM->put_InvokeCustomSetupDlg(ID_SETUP_CURRENCYSETTINGS , TRUE);  
}  
else  
{  
SmpOEM->put_InvokeCustomSetupDlg(ID_SETUP_CURRENCYSETTINGS , FALSE);  
}
```

[Back to ISmpOEMEvents members](#)

ISmpOEMEvents::InvokeCustomTransactionMenuDlg

method InvokeCustomTransactionMenuDlg

```
Sub InvokeCustomTransactionMenuDlg(iDialogType As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	iDialogType	Long	No	-	iDialogType in Long type

Method description

Invoke the Custom Transaction Menu dialog

Example code

```
CComPtr<ISmpOEM> SmpOEM;

CString TransactionMenuCheckBox="True" ;
if(TransactionMenuCheckBox == "True")
{
SmpOEM->put_InvokeCustomTransactionDlg(ID_TRANSACTION_TRANSACTIONDETAILS ,TRUE);
}
else
{
SmpOEM->put_InvokeCustomTransactionDlg(ID_TRANSACTION_TRANSACTIONDETAILS ,FALSE);
}
```

[Back to ISmpOEMEvents members](#)

ISmpOEMEvents::InvokeCustomViewMenu

method InvokeCustomViewMenu

```
Sub InvokeCustomViewMenu(iMenuType As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	iMenuType	Long	No	-	iMenuType in Long type

Method description

Invoke the Custom View Menu dialog

Example code

```
CComPtr<ISmpOEM> SmpOEM;  
  
CString ViewMenuCheckBox="True" ;  
if(ViewMenuCheckBox == "True")  
{  
SmpOEM->put_InvokeCustomViewMenuDlg(ID_VIEW_TOOLBAR_MAINTOOLBAR , TRUE);  
}  
else  
{  
SmpOEM->put_InvokeCustomViewMenuDlg(ID_VIEW_TOOLBAR_MAINTOOLBAR , FALSE);  
}
```

[Back to ISmpOEMEvents members](#)

Coclass: SmpGrid

Interface: ISmpGrid

[Browse members alphabetically](#)

[Browse members by category](#)

[Browse members by use](#)

ISmpGrid members

Properties

Name	Type	HelpString	Category	Frequency of use
AutoSize	Method	method AutoSize	General	Normal
ColumnResize	Property Get/Let	property ColumnResize	General	Normal
GridObj	Property Get	property GridObj	General	Normal
IsCellMerged	Property Get	property IsCellMerged	General	Normal
RowResize	Property Get/Let	property RowResize	General	Normal
SelectedCellCount	Property Get	property SelectedCellCount	General	Normal
SetAutoSizeStyle	Method	method SetAutoSizeStyle	General	Normal
SetFocusCell	Method	method SetFocusCell	General	Normal

[ISmpGrid overview](#)

ISmpGrid::AutoSize

method AutoSize

```
Sub AutoSize
```

No parameters

Method description

This method is used to set the size of the cells of the grid automatically.

[Back to ISmpGrid members](#)

ISmpGrid::SetAutoSizeStyle

method SetAutoSizeStyle

```
Sub SetAutoSizeStyle(nStyle As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	nStyle	Long	No	-	

Method description

This method is used to set the size and style of the cells of the grid automatically.

[Back to ISmpGrid members](#)

ISmpGrid::SetFocusCell

method SetFocusCell

```
Sub SetFocusCell(iRow As Long, iCol As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	iRow	Long	No	-	
2	iCol	Long	No	-	

Method description

This method is used to set a focus cell in the grid

[Back to ISmpGrid members](#)

ISmpGrid::SelectedCellCount

property SelectedCellCount

```
Property Get SelectedCellCount As Long
```

No parameters

[Back to ISmpGrid members](#)

ISmpGrid::RowResize

property RowResize

Property Get/Let RowResize As Long

No parameters

[Back to ISmpGrid members](#)

(C) 1999-2001 My Company All rights reserved

ISmpGrid::IsCellMerged

property IsCellMerged

```
Property Get IsCellMerged(iRow As Long, iCol As Long) As Long
```

Parameters

No	Name	Type	Optional	Default	Description
1	iRow	Long	No	-	
2	iCol	Long	No	-	

[Back to ISmpGrid members](#)

ISmpGrid::ColumnResize

property ColumnResize

Property Get/Let ColumnResize As Long

No parameters

Method description

This method is used to set the size of the column of the grid automatically.

[Back to ISmpGrid members](#)

ISmpGrid::GridObj

property GridObj

Property Get GridObj As Variant

No parameters

[Back to ISmpGrid members](#)

Coclass: SmpGridCtrl

Interface: ISmpGridCtrl

[Browse members alphabetically](#)

[Browse members by category](#)

[Browse members by use](#)

ISmpGridCtrl members

Properties

Name	Type	HelpString	Category	Frequency of use
AutoSize	Method	method AutoSize	General	Normal
DeleteAllImages	Method	method DeleteAllImages	General	Normal
DeleteAllItems	Method	method DeleteAllItems	General	Normal
GridBkgColor	Property Get/Let	property GridBkgColor	General	Normal
GridCtrlObj	Property Get	property GridCtrlObj	General	Normal
RefreshCtrl	Method	method RefreshCtrl	General	Normal
SetBusinessLogo	Method	method SetBusinessLogo	General	Normal
SetCellImage	Method	method SetCellImage	General	Normal
SetCellImageEx	Method	method SetCellImageEx	General	Normal
SetCellText	Method	method SetCellText	General	Normal
SetCellTextAlignment	Method	method SetCellTextAlignment	General	Normal
SetCellTextWrap	Method	method SetCellTextWrap	General	Normal
SetDefaultColumnWidth	Method	method SetDefaultColumnWidth	General	Normal
SetDefaultRowHeight	Method	method SetDefaultRowHeight	General	Normal
SetGridDisplayReadOnly	Method	method SetGridDisplayReadOnly	General	Normal
SetWordWrapMode	Method	method SetWordWrapMode	General	Normal

[ISmpGridCtrl overview](#)

ISmpGridCtrl::SetBusinessLogo

method SetBusinessLogo

```
Sub SetBusinessLogo(Row As Long, Col As Long, Width As Long, Height  
As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	Row	Long	No	-	
2	Col	Long	No	-	
3	Width	Long	No	-	
4	Height	Long	No	-	

Method description

This method is used to set the cell in which the business logo has to be placed in the grid .

[Back to ISmpGridCtrl members](#)

ISmpGridCtrl::SetCellImageEx

method SetCellImageEx

```
Sub SetCellImageEx( Row As Long, Col As Long, ImageResID As Long,  
ModuleHandle As Long, Width As Long, Height As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	Row	Long	No	-	
2	Col	Long	No	-	
3	ImageResID	Long	No	-	
4	ModuleHandle	Long	No	-	
5	Width	Long	No	-	
6	Height	Long	No	-	

Method description

This method is used to set an external image on a selected cell in the grid . The image can be browsed from the external memory and can be placed in any of the selected cell in the grid.

[Back to ISmpGridCtrl members](#)

ISmpGridCtrl::SetWordWrapMode

method SetWordWrapMode

```
Sub SetWordWrapMode(bMode As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	bMode	Long	No	-	

Method description

This method is used to set word wrap property for the grid.

[Back to ISmpGridCtrl members](#)

ISmpGridCtrl::SetCellTextWrap

method SetCellTextWrap

```
Sub SetCellTextWrap(Row As Long, Col As Long, WordWrap As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	Row	Long	No	-	
2	Col	Long	No	-	
3	WordWrap	Long	No	-	

Method description

This method is used to set text wrap property for the cells in the grid.

[Back to ISmpGridCtrl members](#)

ISmpGridCtrl::SetCellImage

method SetCellImage

```
Sub SetCellImage(Row As Long, Col As Long, strImagePath As String,  
Width As Long, Height As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	Row	Long	No	-	
2	Col	Long	No	-	
3	strImagePath	String	No	-	
4	Width	Long	No	-	
5	Height	Long	No	-	

Method description

This method is used to set an image on a selected cell in the grid.

[Back to ISmpGridCtrl members](#)

ISmpGridCtrl::SetGridDisplayReadOnly

method SetGridDisplayReadOnly

```
Sub SetGridDisplayReadOnly(bReadOnly As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	bReadOnly	Long	No	-	

Method description

This method is used to set the grid as read only.

[Back to ISmpGridCtrl members](#)

ISmpGridCtrl::SetDefaultColumnWidth

method SetDefaultColumnWidth

```
Sub SetDefaultColumnWidth(Width As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	Width	Long	No	-	

Method description

This method is used to set a default column width in the grid.

[Back to ISmpGridCtrl members](#)

ISmpGridCtrl::SetCellText

method SetCellText

```
Sub SetCellText( Row As Long, Col As Long, CellText As String,  
TextDisplayOptions As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	Row	Long	No	-	
2	Col	Long	No	-	
3	CellText	String	No	-	
4	TextDisplayOptions	Long	No	-	

Method description

This method is used to set a text on a selected cell in the grid.

[Back to ISmpGridCtrl members](#)

ISmpGridCtrl::SetCellTextAlignment

method SetCellTextAlignment

```
Sub SetCellTextAlignment(Row As Long, Col As Long, Alignment As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	Row	Long	No	-	
2	Col	Long	No	-	
3	Alignment	Long	No	-	

Method description

This method is used to set text alignment in a selected cell in the grid.

[Back to ISmpGridCtrl members](#)

ISmpGridCtrl::SetDefaultRowHeight

method SetDefaultRowHeight

```
Sub SetDefaultRowHeight(Height As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	Height	Long	No	-	

Method description

This method is used to set a default row height in the grid.

[Back to ISmpGridCtrl members](#)

ISmpGridCtrl::GridBkgColor

property GridBkgColor

Property Get/Let GridBkgColor As Long

No parameters

[Back to ISmpGridCtrl members](#)

ISmpGridCtrl::GridCtrlObj

property GridCtrlObj

Property Get GridCtrlObj As Variant

No parameters

[Back to ISmpGridCtrl members](#)

ISmpGridCtrl::AutoSize

method AutoSize

```
Sub AutoSize
```

Parameters

No parameters

Method description

This method is used to set the size of the cells of the grid automatically.

[Back to ISmpGridCtrl members](#)

ISmpGridCtrl::RefreshCtrl

method RefreshCtrl

```
Sub RefreshCtrl
```

Parameters

No parameters

Method description

This method is used to Refresh the existing grid.

[Back to ISmpGridCtrl members](#)

ISmpGridCtrl::DeleteAllImages

method DeleteAllImages

```
Sub DeleteAllImages
```

Parameters

No parameters

Method description

This method is used to remove all the images from the grid.

[Back to ISmpGridCtrl members](#)

ISmpGridCtrl::DeleteAllItems

method DeleteAllItems

```
Sub DeleteAllItems
```

Parameters

No parameters

Method description

This method is used to delete the existing grid.

[Back to ISmpGridCtrl members](#)

Coclass: SmpApp

Interface: ISmpApp

[Browse members alphabetically](#)

[Browse members by category](#)

[Browse members by use](#)

ISmpApp members

Properties

Name	Type	HelpString	Category	Frequency of use
IsRegistered	Property Get	property IsRegistered	General	Normal
SendStatus	Method	method SendStatus	General	Normal
SetAddInInfo	Method	method SetAddInInfo	General	Normal
SetAddinSecurityInfo	Method	method SetAddinSecurityInfo	General	Normal
WindowHandle	Property Get	property WindowHandle	General	Normal

[ISmpApp overview](#)

ISmpApp::IsRegistered

property IsRegistered

Property Get IsRegistered As Long

No parameters

[Back to ISmpApp members](#)

(C) 1999-2001 My Company All rights reserved

ISmpApp::SendStatus

method SendStatus

```
Sub SendStatus(strStatus As String)
```

Parameters

No	Name	Type	Optional	Default	Description
1	strStatus	String	No	-	A BSTR variable to hold status

Method description

Used to send status message

Example code

```
CComPtr<ISmpApp>m_ISmpApp;  
HRESULT hr = m_ISmpApp.CoCreateInstance(CLSID_SmpApp);  
HRESULT HR=m_ISmpApp->SendStatus(bstr_status);
```

[Back to ISmpApp members](#)

ISmpApp::SetAddInInfo

method SetAddInInfo

```
Sub SetAddInInfo(lSessionID As Long, lInstanceHandle As Long,  
strXMLMenuToolbarIDCmdInfo As String, lToobarResSmall As Long,  
lToobarResBig As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	lSessionID	Long	No	-	
2	lInstanceHandle	Long	No	-	
3	strXMLMenuToolbarIDCmdInfo	String	No	-	
4	lToobarResSmall	Long	No	-	
5	lToobarResBig	Long	No	-	

Method description

Used to set addin information

Example code

```
CComPtr<ISmpApp>m_ISmpApp;  
HRESULT hr = m_ISmpApp.CoCreateInstance(CLSID_SmpApp);  
HRESULT HR=m_ISmpApp->SetAddInInfo(GetApp()->m_lSessionID,(long)lApp
```

[Back to ISmpApp members](#)

ISmpApp::SetAddinSecurityInfo

method SetAddinSecurityInfo

```
Sub SetAddinSecurityInfo(lSessionID As Long, strSecurityInfo As String)
```

Parameters

No	Name	Type	Optional	Default	Description
1	lSessionID	Long	No	-	
2	strSecurityInfo	String	No	-	

Method description

Used to set Addin security information

Example code

```
CComPtr<ISmpApp>m_ISmpApp;  
HRESULT hr = m_ISmpApp.CoCreateInstance(CLSID_SmpApp);  
HRESULT HR=m_ISmpApp->SetAddinSecurityInfo(GetApp()->m_lSessionID, st
```

[Back to ISmpApp members](#)

ISmpApp::WindowHandle

property WindowHandle

Property Get WindowHandle As Variant

No parameters

[Back to ISmpApp members](#)

(C) 1999-2001 My Company All rights reserved

Coclass: SmpAddin

Interface: ISmpAddin

[Browse members alphabetically](#)

[Browse members by category](#)

[Browse members by use](#)

ISmpAddin members

Properties

Name	Type	HelpString	Category	Frequency of use
ApplicationLaunched	Method	method ApplicationLaunched	General	Normal
CheckCredentials	Method	method CheckCredentials	General	Normal
DeleteOldData	Method	method DeleteOldData	General	Normal
Initialize	Method	method Initialize	General	Normal
InitializeDatabase	Method	method InitializeDatabase	General	Normal
InvokeAboutBox	Method	method InvokeAboutBox	General	Normal
Uninitialize	Method	method Uninitialize	General	Normal
UpdateAddinCmdUI	Method	method UpdateAddinCmdUI	General	Normal

[ISmpAddin](#) overview

ISmpAddin::ApplicationLaunched

method ApplicationLaunched

```
Sub ApplicationLaunched
```

No parameters

[Back to ISmpAddin members](#)

ISmpAddin::CheckCredentials

method CheckCredentials

```
Sub CheckCredentials(pStrOrganizationName As String, pStrKey As String)
```

Parameters

No	Name	Type	Optional	Default	Description
1	pStrOrganizationName	String	No	-	
2	pStrKey	String	No	-	

[Back to ISmpAddin members](#)

ISmpAddin::DeleteOldData

method DeleteOldData

```
Sub DeleteOldData(strSpecifiedDate As String)
```

Parameters

No	Name	Type	Optional	Default	Description
1	strSpecifiedDate	String	No	-	

[Back to ISmpAddin members](#)

ISmpAddin::Initialize

method Initialize

```
Sub Initialize(lSessionID As Long, pApp As ISmpApp, bFirstTime)
```

Parameters

No	Name	Type	Optional	Default	Description
1	lSessionID	Long	No	-	
2	pApp	ISmpApp	No	-	
3	bFirstTime	Variant	No	-	

[Back to ISmpAddin members](#)

ISmpAddin::InitializeDatabase

method InitializeDatabase

```
Sub InitializeDatabase(lSessionID As Long, plStatus As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	lSessionID	Long	No	-	
2	plStatus	Long	No	-	

[Back to ISmpAddin members](#)

ISmpAddin::InvokeAboutBox

method InvokeAboutBox

```
Sub InvokeAboutBox
```

No parameters

[Back to ISmpAddin members](#)

ISmpAddin::Uninitialize

method Uninitialize

```
Sub Uninitialize(lSessionID As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	lSessionID	Long	No	-	

[Back to ISmpAddin members](#)

ISmpAddin::UpdateAddinCmdUI

method UpdateAddinCmdUI

```
Sub UpdateAddinCmdUI(lCommandID As Long, pbEnable As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	lCommandID	Long	No	-	
2	pbEnable	Long	No	-	

[Back to ISmpAddin members](#)

Coclass: Accounts

Interface: IAccounts

[Browse members alphabetically](#)

[Browse members by category](#)

[Browse members by use](#)

IAccounts members

Properties

Name	Type	HelpString	Category	Frequency of use
AddToShopBalance	Method	method AddToShopBalance	General	Normal
InvokeAcceptPaymentDialog	Method	method InvokeAcceptPaymentDialog	General	Normal
InvokeRefundToCustomerDlg	Method	method InvokeRefundToCustomerDlg	General	Normal
SubstractFromShopBalance	Method	method SubstractFromShopBalance	General	Normal

[IAccounts overview](#)

IAccounts::AddToShopBalance

method AddToShopBalance

```
Sub AddToShopBalance(dBalanceToAdd As Double)
```

Parameters

No	Name	Type	Optional	Default	Description
1	dBalanceToAdd	Double	No	-	Balance to add in double type

Method description

Add amount to the shop balance

Example code

```
CCoMPtr<IAccounts>m_IAccountsInterface;
HRESULT hr;
hr=m_IAccountsInterface.CoCreateInstance(CLSID_Accounts);
if(FAILED(hr))
{
    AfxMessageBox(_T("IAccountsInterface initialisation failed"))
    return FALSE;
}
double dVal;
CString strAddVal;
m_EditAddVal.GetWindowText(strAddVal);
if(strAddVal!="")
{
#ifdef UNICODE
    dVal = wcstod((strAddVal), NULL);
#else
    dVal=atof((LPCTSTR)strAddVal);
#endif
BOOL bet=m_IAccountsInterface->AddToShopBalance(dVal);
if(bet)
{
    AfxMessageBox(_T("Value successfully added to the shop balan
}
```

```
else
{
    AfxMessageBox(_T("Failed too add value to the shop balance"))
}
```

[Back to IAccounts members](#)

(C) 1999-2001 My Company All rights reserved

IAccounts::InvokeAcceptPaymentDialog

method InvokeAcceptPaymentDialog

```
Sub InvokeAcceptPaymentDialog(varCustomerID)
```

Parameters

No	Name	Type	Optional	Default	Description
1	varCustomerID	Variant	No	-	Customer id in variant type

Method description

Invoke the Accept payment dialog

Example code

```
VARIANT varCusId;  
varCusId.iVal=1;  
CComPtr<IAccounts>m_IAccountsInterface;  
HRESULT hr;  
hr=m_IAccountsInterface.CoCreateInstance(CLSID_Accounts);  
if(FAILED(hr))  
{  
    AfxMessageBox(_T("IAccountsInterface initialisation failed"))  
    return FALSE;  
}  
m_IAccountsInterface->InvokeAcceptPaymentDialog(varCusId);
```

[Back to IAccounts members](#)

IAccounts::InvokeRefundToCustomerDlg

method InvokeRefundToCustomerDlg

```
Sub InvokeRefundToCustomerDlg(varCustomerID)
```

Parameters

No	Name	Type	Optional	Default	Description
1	varCustomerID	Variant	No	-	Customer id in variant type

Method description

Invoke the refund to customer dialog

Example code

```
VARIANT varCusId;  
varCusId.iVal=1;  
CComPtr<IAccounts>m_IAccountsInterface;  
HRESULT hr;  
hr=m_IAccountsInterface.CoCreateInstance(CLSID_Accounts);  
if(FAILED(hr))  
{  
    AfxMessageBox(_T("IAccountsInterface initialisation failed"))  
    return FALSE;  
}  
m_IAccountsInterface->InvokeRefundToCustomerDlg(varCusId);
```

[Back to IAccounts members](#)

IAccounts::SubstractFromShopBalance

method SubstractFromShopBalance

```
Sub SubstractFromShopBalance(dBalanceToSubstract As Double)
```

Parameters

No	Name	Type	Optional	Default	Description
1	dBalanceToSubstract	Double	No	-	Balance to substract in double type

Method description

Substract amount from the shop balance

Example code

```
try
{
    double dVal;
    CString strSubVal;
    m_EditSubVal.GetWindowText(strSubVal);
    if(strSubVal!="")
    {
        try
        {
#ifndef UNICODE
            dVal = wcstod((strSubVal), NULL);
#else
            dVal=atof((LPCTSTR)strSubVal);
#endif
            if(dVal<=0)
            {
                AfxMessageBox(_T("Please che
                return;
            }
        }
        catch(...)
        {

```

```
        AfxMessageBox(_T("Please enter a val
                    return;
    }

    long lVal=m_IAccountsInterface->SubstractFro
    if(lVal>0)
    {
        AfxMessageBox(_T("Value successfully
    }
    else
    {
        AfxMessageBox(_T("Failed to substrac
    }

    else
    {
        AfxMessageBox(_T("Please enter value for sub
        return;
    }

}
catch(...)
{
    AfxMessageBox(_T("Error while subtracting value fro
}
```

[Back to IAccounts members](#)

Coclass: AccountsEvents

Interface: IAccountsEvents

[Browse members alphabetically](#)

[Browse members by category](#)

[Browse members by use](#)

IAccountsEvents members

Properties

Name	Type	HelpString	Category	Frequency of use
AddAdvancedReportPage	Method	method AddAdvancedReportPage	General	Normal
OnAccountReport	Method	method OnAccountReport	General	Normal
OnTransactionAccountDetails	Method	method OnTransactionAccountDetails	General	Normal

[IAccountsEvents overview](#)

IAccountsEvents::AddAdvancedReportPage

method AddAdvancedReportPage

```
Sub AddAdvancedReportPage(lReportType As Long, pSheet)
```

Parameters

No	Name	Type	Optional	Default	Description
1	lReportType	Long	No	-	
2	pSheet	Variant	No	-	

[Back to IAccountsEvents members](#)

IAccountsEvents::OnAccountReport

method OnAccountReport

```
Sub OnAccountReport(lReportType As Long, strValue1 As String,  
strValue2 As String, varGenericReport)
```

Parameters

No	Name	Type	Optional	Default	Description
1	lReportType	Long	No	-	
2	strValue1	String	No	-	
3	strValue2	String	No	-	
4	varGenericReport	Variant	No	-	

[Back to IAccountsEvents members](#)

IAccountsEvents::OnTransactionAccountDetails

method OnTransactionAccountDetails

```
Sub OnTransactionAccountDetails(lType As Long, varValue1,  
varValue2, varValue3, varValue4)
```

Parameters

No	Name	Type	Optional	Default	Description
1	lType	Long	No	-	
2	varValue1	Variant	No	-	
3	varValue2	Variant	No	-	
4	varValue3	Variant	No	-	
5	varValue4	Variant	No	-	

[Back to IAccountsEvents members](#)

Coclass: SmpDialogEvents

Interface: ISmpDialogEvents

[Browse members alphabetically](#)

[Browse members by category](#)

[Browse members by use](#)

ISmpDialogEvents members

Properties

Name	Type	HelpString	Category	Frequency of use
OnDialogWndProc	Method	method OnDialogWndProc	General	Normal

[ISmpDialogEvents overview](#)

ISmpDialogEvents::OnDialogWndProc

method OnDialogWndProc

```
Sub OnDialogWndProc(hWndHandle, lDialogID As Long, message As Long,  
wParam, lParam, lDialogueType As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	hWndHandle	Variant	No	-	
2	lDialogID	Long	No	-	
3	message	Long	No	-	
4	wParam	Variant	No	-	
5	lParam	Variant	No	-	
6	lDialogueType	Long	No	-	

[Back to ISmpDialogEvents members](#)

Coclass: SmpReport

Interface: ISmpReport

[Browse members alphabetically](#)

[Browse members by category](#)

[Browse members by use](#)

ISmpReport members

Properties

Name	Type	HelpString	Category	Frequency of use
FillReport	Method	method FillReport	General	Normal
GetBodyFormat	Method	method GetBodyFormat	General	Normal
GetFooterFormat	Method	method GetFooterFormat	General	Normal
GetFooterInfo	Method	method GetFooterInfo	General	Normal
GetHeaderFormat	Method	method GetHeaderFormat	General	Normal
GetHeaderInfo	Method	method GetHeaderInfo	General	Normal
PrintReport	Method	method PrintReport	General	Normal
ResetContent	Method	method ResetContent	General	Normal
SetBodyFormat	Method	method SetBodyFormat	General	Normal
SetFooterFormat	Method	method SetFooterFormat	General	Normal
SetFooterInfo	Method	method SetFooterInfo	General	Normal
SetHeaderFormat	Method	method SetHeaderFormat	General	Normal
SetHeaderInfo	Method	method SetHeaderInfo	General	Normal

[ISmpReport](#) overview

ISmpReport::FillReport

method FillReport

```
Sub FillReport(strSQLQuery As String)
```

Parameters

No	Name	Type	Optional	Default	Description
1	strSQLQuery	String	No	-	A BSTR value containing the SQL Query to retrieve data from database

Method description

It is used to fill the report

Example code

```
CComPtr<ISmpReport>m_SmpReport;  
  
HRESULT hr=SmpReport.CoCreateInstance(CLSID_SmpReport);  
  
CString strSQLQuery=_T(""+SELECT * FROM "+ TableName);  
bstrSQLQuery=strSQLQuery.AllocSysString();  
  
m_SmpReport->FillReport(m_bstrSQLQuery);
```

[Back to ISmpReport members](#)

ISmpReport::GetBodyFormat

method GetBodyFormat

```
Sub GetBodyFormat(strFont As String, piSize As Long, piColor As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	strFont	String	No	-	Pointer to a BSTR value to store font type of the body text
2	piSize	Long	No	-	Pointer to a long value to store size of the body text
3	piColor	Long	No	-	Pointer to a long value for storing the colour of the body text

Method description

It is used for getting the current body format information

Example code

```
CComPtr<ISmpReport>m_SmpReport;  
  
HRESULT hr=SmpReport.CoCreateInstance(CLSID_SmpReport);  
  
BSTR bstrFont;  
Long lSize,lColour;  
  
m_SmpReport->GetBodyFormat(&bstrFont,&lSize,&lColour);
```

[Back to ISmpReport members](#)

ISmpReport::GetFooterFormat

method GetFooterFormat

```
Sub GetFooterFormat(strFont As String, piSize As Long, piColor As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	strFont	String	No	-	Pointer to a BSTR value to store font type of the body text
2	piSize	Long	No	-	Pointer to a long value to store size of the body text
3	piColor	Long	No	-	Pointer to a long value for storing the colour of the body text

Method description

It is used for getting the current footer format information

Example code

```
CComPtr<ISmpReport>m_SmpReport;  
  
HRESULT hr=SmpReport.CoCreateInstance(CLSID_SmpReport);  
  
BSTR bstrFont;  
Long lSize,lColour;  
  
m_SmpReport->GetFooterFormat(&bstrFont,&lSize,&lColour);
```

[Back to ISmpReport members](#)

ISmpReport::GetFooterInfo

method GetFooterInfo

```
Sub GetFooterInfo(pFooter1 As String, pFooter2 As String, pFooter3  
As String)
```

Parameters

No	Name	Type	Optional	Default	Description
1	pFooter1	String	No	-	Pointer to BSTR value to store the footer1 text
2	pFooter2	String	No	-	Pointer to BSTR value to store the footer2 text
3	pFooter3	String	No	-	Pointer to BSTR value to store the footer3 text

Method description

It is used for getting the current footer information

Example code

```
CComPtr<ISmpReport>m_SmpReport;  
  
HRESULT hr=SmpReport.CoCreateInstance(CLSID_SmpReport);  
  
BSTR bstrFooter1,bstrFooter2,bstrFooter3;  
  
m_SmpReport->GetFooterInfo(&bstrFooter1,&bstrFooter2,&bstrFooter3);
```

[Back to ISmpReport members](#)

ISmpReport::GetHeaderFormat

method GetHeaderFormat

```
Sub GetHeaderFormat(strFont As String, piSize As Long, piColor As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	strFont	String	No	-	Pointer to a BSTR value to store font type of the body text
2	piSize	Long	No	-	Pointer to a long value to store size of the body text
3	piColor	Long	No	-	Pointer to a long value for storing the colour of the body text

Method description

It is used for getting the current header format information

Example code

```
CComPtr<ISmpReport>m_SmpReport;  
  
HRESULT hr=SmpReport.CoCreateInstance(CLSID_SmpReport);  
  
BSTR bstrFont;  
Long lSize,lColour;  
  
m_SmpReport->GetHeaderFormat(&bstrFont,&lSize,&lColour);
```

[Back to ISmpReport members](#)

ISmpReport::GetHeaderInfo

method GetHeaderInfo

```
Sub GetHeaderInfo(pMainHeading1 As String, pSubHeading1 As String,  
pMainHeading2 As String, pSubHeading2 As String, pHeaderImagePath  
As String)
```

Parameters

No	Name	Type	Optional	Default	Description
1	pMainHeading1	String	No	-	Pointer to a BSTR value to store the main heading 1 text
2	pSubHeading1	String	No	-	Pointer to a BSTR value to store the sub heading 1 text
3	pMainHeading2	String	No	-	Pointer to a BSTR value to store the main heading 2 text
4	pSubHeading2	String	No	-	Pointer to a BSTR value to store the sub heading 1 text
5	pHeaderImagePath	String	No	-	Pointer to a BSTR value to store the header image path

Method description

It is used for getting the current header information

Example code

```
CComPtr<ISmpReport>m_SmpReport;  
  
HRESULT hr=SmpReport.CoCreateInstance(CLSID_SmpReport);  
  
BSTR bstrMainHeading1,bstrSubHeading1,bstrMainHeading2,bstrSubHeadin  
m_SmpReport->GetHeaderInfo(&m_bstrMainHeading1,&m_bstrSubHeading1,&r
```

[Back to ISmpReport members](#)

ISmpReport::PrintReport

method PrintReport

```
Sub PrintReport
```

No parameters

Method description

It is used to invoke the print dialog

Example code

```
CComPtr<ISmpReport>m_SmpReport;  
HRESULT hr=SmpReport.CoCreateInstance(CLSID_SmpReport);  
m_SmpReport->PrintReport();
```

[Back to ISmpReport members](#)

ISmpReport::ResetContent

method ResetContent

```
Sub ResetContent
```

No parameters

Method description

It is used to reseting the contents information that are used for displaying reports

Example code

```
CComPtr<ISmpReport>m_SmpReport;  
HRESULT hr=SmpReport.CoCreateInstance(CLSID_SmpReport);  
m_SmpReport->ResetContent();
```

[Back to ISmpReport members](#)

ISmpReport::SetBodyFormat

method SetBodyFormat

```
Sub SetBodyFormat(strFont As String, iSize As Long, Color As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	strFont	String	No	-	Pointer to a BSTR value to store font type of the body text
2	iSize	Long	No	-	Pointer to a long value to store size of the body text
3	Color	Long	No	-	Pointer to a long value for storing the colour of the body text

Method description

It is used for setting the body format

Example code

```
CComPtr<ISmpReport>m_SmpReport;  
  
HRESULT hr=SmpReport.CoCreateInstance(CLSID_SmpReport);  
  
BSTR bstrFont;  
Long lSize,lColour;  
  
m_SmpReport->SetBodyFormat(bstrFont,lSize,lColour);
```

[Back to ISmpReport members](#)

ISmpReport::SetFooterFormat

method SetFooterFormat

```
Sub SetFooterFormat(strFont As String, iSize As Long, Color As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	strFont	String	No	-	
2	iSize	Long	No	-	
3	Color	Long	No	-	

Method description

It is used for setting the footer format.

Example code

```
CComPtr<ISmpReport>m_SmpReport;  
  
HRESULT hr=SmpReport.CoCreateInstance(CLSID_SmpReport);  
  
BSTR bstrFont;  
Long lSize,lColour;  
  
m_SmpReport->SetFooterFormat(bstrFont,lSize,lColour);
```

[Back to ISmpReport members](#)

ISmpReport::SetFooterInfo

method SetFooterInfo

```
Sub SetFooterInfo(strFooter1 As String, strFooter2 As String,  
strFooter3 As String)
```

Parameters

No	Name	Type	Optional	Default	Description
1	strFooter1	String	No	-	Pointer to BSTR value to store the footer1 text
2	strFooter2	String	No	-	Pointer to BSTR value to store the footer2 text
3	strFooter3	String	No	-	Pointer to BSTR value to store the footer3 text

Method description

It is used for setting the footer information

Example code

```
CComPtr<ISmpReport>m_SmpReport;  
  
HRESULT hr=SmpReport.CoCreateInstance(CLSID_SmpReport);  
  
BSTR bstrFooter1,bstrFooter2,bstrFooter3;  
  
m_SmpReport->SetFooterInfo(bstrFooter1,bstrFooter2,bstrFooter3);
```

[Back to ISmpReport members](#)

ISmpReport::SetHeaderFormat

method SetHeaderFormat

```
Sub SetHeaderFormat(strFont As String, iSize As Long, Color As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	strFont	String	No	-	Pointer to a BSTR value to store font type of the body text
2	iSize	Long	No	-	Pointer to a long value to store size of the body text
3	Color	Long	No	-	Pointer to a long value for storing the colour of the body text

Method description

It is used for setting the header format

Example code

```
CComPtr<ISmpReport>m_SmpReport;  
  
HRESULT hr=SmpReport.CoCreateInstance(CLSID_SmpReport);  
  
BSTR bstrFont;  
Long lSize,lColour;  
  
m_SmpReport->SetHeaderFormat(bstrFont,lSize,lColour);
```

[Back to ISmpReport members](#)

ISmpReport::SetHeaderInfo

method SetHeaderInfo

```
Sub SetHeaderInfo(strMainHeading1 As String, strSubHeading1 As  
String, strMainHeading2 As String, strSubHeading2 As String,  
strHeaderImagePath As String)
```

Parameters

No	Name	Type	Optional	Default	Description
1	strMainHeading1	String	No	-	Pointer to a BSTR value to store the main heading1 text
2	strSubHeading1	String	No	-	Pointer to a BSTR value to store the sub heading 1 text
3	strMainHeading2	String	No	-	Pointer to a BSTR value to store the main heading 2 text
4	strSubHeading2	String	No	-	Pointer to a BSTR value to store the sub heading 1 text
5	strHeaderImagePath	String	No	-	Pointer to a BSTR value to store the header image path

Method description

It is used for setting the header information

Example code

```
BSTR bstrMainHeading1,bstrSubHeading1,bstrMainHeading2,bstrSubHeadin  
m_SmpReport->SetHeaderInfo(bstrMainHeading1,bstrSubHeading1,bstrMain
```

[Back to ISmpReport members](#)

Coclass: ISmpCommands

Interface: IIISmpCommands

[Browse members alphabetically](#)

[Browse members by category](#)

[Browse members by use](#)

IISmpCommands members

Properties

<i>Name</i>	<i>Type</i>	<i>HelpString</i>	<i>Category</i>	<i>Frequency of use</i>
MenuCommandEx	Property Get	property MenuCommandEx	General	Normal
MenuCommandID	Property Get	property MenuCommandID	General	Normal
MenuString	Property Get	property MenuString	General	Normal
NoOfCommands	Property Get	property NoOfCommands	General	Normal

[IIISmpCommands overview](#)

IISmpCommands::MenuCommandEx

property MenuCommandEx

```
Property Get MenuCommandEx(lSessionID As Long, strFunctionName As String) As Long
```

Parameters

No	Name	Type	Optional	Default	Description
1	lSessionID	Long	No	-	Session id in long format
2	strFunctionName	String	No	-	Function name in BSTR type

Property description

Retrieve the Menu CommandEx

Example code

```
CComPtr<IISmpCommands>m_IISMPCommands;
HRESULT hr;
CString strFunName;
long lComdEx;

hr=m_IISMPCommands.CoCreateInstance(CLSID_ISmpCommands);
if(FAILED(hr))
{
    AfxMessageBox(_T("IISmpCommandsInterface initialisation fail
        return FALSE;
}
m_IISMPCommands->get_MenuCommandEx(m_lSessionID,strFunName.AllocSysS
```

[Back to IISmpCommands members](#)

IISmpCommands::MenuCommandID

property MenuCommandID

```
Property Get MenuCommandID(lSessionID As Long, strMenuStrings As String) As Long
```

Parameters

No	Name	Type	Optional	Default	Description
1	lSessionID	Long	No	-	Session id in long format
2	strMenuStrings	String	No	-	Menu string in BSTR type

Property description

Retrieve the Menu command Id

Example code

```
BSTR bstrMenuString;
long lComdId;
CComPtr<IISmpCommands>m_IISMPCommands;
HRESULT hr;

hr=m_IISMPCommands.CoCreateInstance(CLSID_ISmpCommands);
if(FAILED(hr))
{
    AfxMessageBox(_T("IISmpCommandsInterface initialisation fail
        return FALSE;
}
m_IISMPCommands->get_MenuCommandID(m_lSessionID,bstrMenuString,&lCom
```

[Back to IISmpCommands members](#)

IISmpCommands::MenuString

property MenuString

```
Property Get MenuString(lSessionID As Long, iCommandID As Long) As String
```

Parameters

No	Name	Type	Optional	Default	Description
1	lSessionID	Long	No	-	SessionId in long type
2	iCommandID	Long	No	-	CommandId in long type

Property description

Retrieve the Menu string

Example code

```
CComPtr<IISmpCommands>m_IISMPCommands;
HRESULT hr;
BSTR bstrMenuString;
long lCmdID;

hr=m_IISMPCommands.CoCreateInstance(CLSID_ISmpCommands);
if(FAILED(hr))
{
    AfxMessageBox(_T("IISmpCommandsInterface initialisation fail
    return FALSE;
}

m_IISMPCommands->get

CString strMenuString(bstrMenuString);

MessageBox(strMenuString,_T("Menu String"),MB_ICONINFORMATION|MB_OK)
```

[Back to IISmpCommands members](#)

IISmpCommands::NoOfCommands

property NoOfCommands

```
Property Get NoOfCommands(lSessionID As Long, strFunctionName As String) As Long
```

Parameters

No	Name	Type	Optional	Default	Description
1	lSessionID	Long	No	-	Session id in long format
2	strFunctionName	String	No	-	Function name in BSTR type

Property description

Retrieve the Number of Commands

Example code

```
CComPtr<IISmpCommands>m_IISMPCommands;
HRESULT hr;
CString strFunName;

hr=m_IISMPCommands.CoCreateInstance(CLSID_ISmpCommands);
if(FAILED(hr))
{
    AfxMessageBox(_T("IISmpCommandsInterface initialisation fail
    return FALSE;
}

m_IISMPCommands->get_NoOfCommands(m_lSessionID,strFunName.AllocSysSt
```

[Back to IISmpCommands members](#)

Coclass: ISmpGenericReport

Interface: IIISmpGenericReport

[Browse members alphabetically](#)

[Browse members by category](#)

[Browse members by use](#)

IISmpGenericReport members

Properties

Name	Type	HelpString	Category	Frequency of use
AddBodyContents	Method	method AddBodyContents	General	Normal
AddBodyContentsEx	Method	method AddBodyContentsEx	General	Normal
AddFooterContents	Method	method AddFooterContents	General	Normal
AddFooterContentsEx	Method	method AddFooterContentsEx	General	Normal
AddMergeInfo	Method	method AddMergeInfo	General	Normal
AddReportHeading	Method	method AddReportHeading	General	Normal
AddReportHeadingEx	Method	method AddReportHeadingEx	General	Normal
BodyCellArrayCount	Property Get	property BodyCellArrayCount	General	Normal
BodyItem	Property Get	property BodyItem	General	Normal
BodyProperties	Property Get/Let	property BodyProperties	General	Normal
FillReport	Method	method FillReport	General	Normal
FooterCellArrayCount	Property Get	property FooterCellArrayCount	General	Normal
FooterItem	Property Get	property FooterItem	General	Normal
FooterProperties	Property Get/Let	property FooterProperties	General	Normal
GenericReportObj	Property Get	property GenericReportObj	General	Normal
GenericReportProperties	Property Get/Let	property GenericReportProperties	General	Normal
HeaderCellArrayCount	Property Get	property HeaderCellArrayCount	General	Normal
HeaderItem	Property Get	property HeaderItem	General	Normal
HeaderProperties	Property Get/Let	property HeaderProperties	General	Normal
HeadingItalic	Property Get/Let	property HeadingItalic	General	Normal
ItemCount	Property Get/Let	property ItemCount	General	Normal
MergeCellProperties	Property Get/Let	property MergeCellProperties	General	Normal
RemoveAllContents	Method	method RemoveAllContents	General	Normal
RemoveBodyContents	Method	method RemoveBodyContents	General	Normal
RemoveFooterContents	Method	method RemoveFooterContents	General	Normal
RemoveHeaderContents	Method	method RemoveHeaderContents	General	Normal
RemoveLastFooterContent	Method	method RemoveLastFooterContent	General	Normal

ReportType	Property Get/Let	property ReportType	General	Normal
SetBodySize	Method	method SetBodySize	General	Normal
SetFooterSize	Method	method SetFooterSize	General	Normal
SetGenericReportObj	Method	method SetGenericReportObj	General	Normal
SetHeaderMargin	Method	method SetHeaderMargin	General	Normal
SetHeaderSize	Method	method SetHeaderSize	General	Normal

IISmpGenericReport overview

IISmpGenericReport::AddBodyContents

method AddBodyContents

```
Sub AddBodyContents(iStartRow As Long, iStartCol As Long, iEndRow  
As Long, iEndCol As Long, strBodyContents As String, dwAlign As  
Long, ContentType As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	iStartRow	Long	No	-	
2	iStartCol	Long	No	-	
3	iEndRow	Long	No	-	
4	iEndCol	Long	No	-	
5	strBodyContents	String	No	-	
6	dwAlign	Long	No	-	
7	ContentType	Long	No	-	

[Back to IISmpGenericReport members](#)

IISmpGenericReport::AddBodyContentsEx

method AddBodyContentsEx

```
Sub AddBodyContentsEx(iRow As Long, iCol As Long, strBodyContents  
As String, dwAlign As Long, ContentType As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	iRow	Long	No	-	
2	iCol	Long	No	-	
3	strBodyContents	String	No	-	
4	dwAlign	Long	No	-	
5	ContentType	Long	No	-	

[Back to IISmpGenericReport members](#)

IIISmpGenericReport::AddFooterContents

method AddFooterContents

```
Sub AddFooterContents(iSatrtRow As Long, iStartCol As Long, iEndRow  
As Long, iEndCol As Long, strFooterContents As String, dwAlign As  
Long, ContentType As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	iSatrtRow	Long	No	-	
2	iStartCol	Long	No	-	
3	iEndRow	Long	No	-	
4	iEndCol	Long	No	-	
5	strFooterContents	String	No	-	
6	dwAlign	Long	No	-	
7	ContentType	Long	No	-	

[Back to IIISmpGenericReport members](#)

IISmpGenericReport::AddFooterContentsEx

method AddFooterContentsEx

```
Sub AddFooterContentsEx(iRow As Long, iCol As Long,  
strFooterContents As String, dwAlign As Long, ContentType As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	iRow	Long	No	-	
2	iCol	Long	No	-	
3	strFooterContents	String	No	-	
4	dwAlign	Long	No	-	
5	ContentType	Long	No	-	

[Back to IISmpGenericReport members](#)

IISmpGenericReport::AddMergeInfo

method AddMergeInfo

```
Sub AddMergeInfo(iRow As Long, iCol As Long, iMaxRow As Long,  
iMaxCol As Long, strText As String)
```

Parameters

No	Name	Type	Optional	Default	Description
1	iRow	Long	No	-	
2	iCol	Long	No	-	
3	iMaxRow	Long	No	-	
4	iMaxCol	Long	No	-	
5	strText	String	No	-	

[Back to IISmpGenericReport members](#)

IISmpGenericReport::AddReportHeading

method AddReportHeading

```
Sub AddReportHeading(iStartRow As Long, iStartCol As Long, iEndRow  
As Long, iEndCol As Long, strHeading As String, dwAlign As Long,  
ContentType As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	iStartRow	Long	No	-	
2	iStartCol	Long	No	-	
3	iEndRow	Long	No	-	
4	iEndCol	Long	No	-	
5	strHeading	String	No	-	
6	dwAlign	Long	No	-	
7	ContentType	Long	No	-	

[Back to IISmpGenericReport members](#)

IISmpGenericReport::AddReportHeadingEx

method AddReportHeadingEx

```
Sub AddReportHeadingEx(iRow As Long, iCol As Long, strHeading As String, dwAlign As Long, ContentType As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	iRow	Long	No	-	
2	iCol	Long	No	-	
3	strHeading	String	No	-	
4	dwAlign	Long	No	-	
5	ContentType	Long	No	-	

[Back to IISmpGenericReport members](#)

IISmpGenericReport::BodyCellArrayCount

property BodyCellArrayCount

```
Property Get BodyCellArrayCount As Long
```

No parameters

[Back to IISmpGenericReport members](#)

IIISmpGenericReport::BodyItem

property BodyItem

```
Property Get BodyItem(lIndex As Long) As IItem
```

Parameters

No	Name	Type	Optional	Default	Description
1	lIndex	Long	No	-	

[Back to IIISmpGenericReport members](#)

IISmpGenericReport::BodyProperties

property BodyProperties

Property Get/Let BodyProperties As ISmpReportItemAttributes

No parameters

[Back to IISmpGenericReport members](#)

(C) 1999-2001 My Company All rights reserved

IISmpGenericReport::FillReport

method FillReport

```
Sub FillReport
```

No parameters

[Back to IISmpGenericReport members](#)

IISmpGenericReport::FooterCellArrayCount

property FooterCellArrayCount

```
Property Get FooterCellArrayCount As Long
```

No parameters

[Back to IISmpGenericReport members](#)

IISmpGenericReport::FooterItem

property FooterItem

```
Property Get FooterItem(lIndex As Long) As IItem
```

Parameters

No	Name	Type	Optional	Default	Description
1	lIndex	Long	No	-	

[Back to IISmpGenericReport members](#)

IISmpGenericReport::FooterProperties

property FooterProperties

Property Get/Let FooterProperties As ISmpReportItemAttributes

No parameters

[Back to IISmpGenericReport members](#)

(C) 1999-2001 My Company All rights reserved

IISmpGenericReport::GenericReportObj

property GenericReportObj

Property Get GenericReportObj As Variant

No parameters

[Back to IISmpGenericReport members](#)

IISmpGenericReport::GenericReportProperties

property GenericReportProperties

Property Get/Let GenericReportProperties As
ISmpReportItemAttributes

No parameters

[Back to IISmpGenericReport members](#)

IISmpGenericReport::HeaderCellArrayCount

property HeaderCellArrayCount

Property Get HeaderCellArrayCount As Long

No parameters

[Back to IISmpGenericReport members](#)

(C) 1999-2001 My Company All rights reserved

IISmpGenericReport::HeaderItem

property HeaderItem

Property Get HeaderItem(lIndex As Long) As IItem

Parameters

No	Name	Type	Optional	Default	Description
1	lIndex	Long	No	-	

[Back to IISmpGenericReport members](#)

IISmpGenericReport::HeaderProperties

property HeaderProperties

Property Get/Let HeaderProperties As ISmpReportItemAttributes

No parameters

[Back to IISmpGenericReport members](#)

(C) 1999-2001 My Company All rights reserved

IISmpGenericReport::HeadingItalic

property HeadingItalic

Property Get/Let HeadingItalic As Long

No parameters

[Back to IISmpGenericReport members](#)

(C) 1999-2001 My Company All rights reserved

IISmpGenericReport::ItemCount

property ItemCount

Property Get/Let ItemCount As Long

No parameters

[Back to IISmpGenericReport members](#)

(C) 1999-2001 My Company All rights reserved

IISmpGenericReport::MergeCellProperties

property MergeCellProperties

Property Get/Let MergeCellProperties As ISmpReportItemAttributes

No parameters

[Back to IISmpGenericReport members](#)

(C) 1999-2001 My Company All rights reserved

IISmpGenericReport::RemoveAllContents

method RemoveAllContents

```
Sub RemoveAllContents
```

No parameters

[Back to IISmpGenericReport members](#)

IISmpGenericReport::RemoveBodyContents

method RemoveBodyContents

```
Sub RemoveBodyContents
```

No parameters

[Back to IISmpGenericReport members](#)

IISmpGenericReport::RemoveFooterContents

method RemoveFooterContents

```
Sub RemoveFooterContents
```

No parameters

[Back to IISmpGenericReport members](#)

IISmpGenericReport::RemoveHeaderContents

method RemoveHeaderContents

```
Sub RemoveHeaderContents
```

No parameters

[Back to IISmpGenericReport members](#)

IISmpGenericReport::RemoveLastFooterContent

method RemoveLastFooterContent

```
Sub RemoveLastFooterContent
```

No parameters

[Back to IISmpGenericReport members](#)

IISmpGenericReport::ReportType

property ReportType

Property Get/Let ReportType As Long

No parameters

[Back to IISmpGenericReport members](#)

(C) 1999-2001 My Company All rights reserved

IIISmpGenericReport::SetBodySize

method SetBodySize

```
Sub SetBodySize(lBodySize As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	lBodySize	Long	No	-	

[Back to IIISmpGenericReport members](#)

IISmpGenericReport::SetFooterSize

method SetFooterSize

```
Sub SetFooterSize(lFoterSize As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	lFoterSize	Long	No	-	

[Back to IISmpGenericReport members](#)

IISmpGenericReport::SetGenericReportObj

method SetGenericReportObj

```
Sub SetGenericReportObj(varGenericReport)
```

Parameters

No	Name	Type	Optional	Default	Description
1	varGenericReport	Variant	No	-	

[Back to IISmpGenericReport members](#)

IISmpGenericReport::SetHeaderMargin

method SetHeaderMargin

```
Sub SetHeaderMargin(iLeft As Long, iRight As Long, iTop As Long,  
iBottom As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	iLeft	Long	No	-	
2	iRight	Long	No	-	
3	iTop	Long	No	-	
4	iBottom	Long	No	-	

[Back to IISmpGenericReport members](#)

IISmpGenericReport::SetHeaderSize

method SetHeaderSize

```
Sub SetHeaderSize(lHeaderSize As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	lHeaderSize	Long	No	-	

[Back to IISmpGenericReport members](#)

Coclass: SmpView

Interface: ISmpView

[Browse members alphabetically](#)

[Browse members by category](#)

[Browse members by use](#)

ISmpView members

Properties

Name	Type	HelpString	Category	Frequency of use
PrintInDosMode	Method	method PrintInDosMode	General	Normal
PrintReport	Method	method PrintReport	General	Normal

[ISmpView overview](#)

ISmpView::PrintInDosMode

method PrintInDosMode

```
Sub PrintInDosMode
```

Parameters

No parameters

Method Description

This is used to generate Report in DOS mode.

[Back to ISmpView members](#)

ISmpView::PrintReport

method PrintReport

```
Sub PrintReport
```

Parameters

No parameters

Method Description

This is used to generate Report.

[Back to ISmpView members](#)

Coclass: SmpPluginTab

Interface: ISmpPluginTab

[Browse members alphabetically](#)

[Browse members by category](#)

[Browse members by use](#)

ISmpPluginTab members

Properties

Name	Type	HelpString	Category	Frequency of use
AddSmpPage	Method	method AddSmpPage	General	Normal
AddView	Method	method AddView	General	Normal
CreateFormView	Method	method CreateFormView	General	Normal
CreateView	Method	method CreateView	General	Normal
CreateWinFormsView	Method	method CreateWinFormsView	General	Normal
GetWindowRect	Method	method GetWindowRect	General	Normal
SetCurrentView	Method	method SetCurrentView	General	Normal
WindowHandle	Property Get	property WindowHandle	General	Normal

[ISmpPluginTab overview](#)

ISmpPluginTab::AddSmpPage

method AddSmpPage

```
Sub AddSmpPage(pPage)
```

Parameters

No	Name	Type	Optional	Default	Description
1	pPage	Variant	No	-	Represents the new Property page

Method description

Adds a new Property page tab

Example code

```
CComPtr<ISmpPluginTab>m_SmpPluginTab  
HRESULT hr = m_SmpPluginTab.CoCreateInstance(CLSID_SmpPluginTab);  
m_SmpPluginTab->AddSmpPage(pPage)
```

[Back to ISmpPluginTab members](#)

ISmpPluginTab::AddView

method AddView

```
Sub AddView(sLabel As String, pView, sTooltip As String, plIndex As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	sLabel	String	No	-	Label of the new tab
2	pView	Variant	No	-	pointer representing the new view
3	sTooltip	String	No	-	Tooltip for the new tab
4	plIndex	Long	No	-	Index of the new tab view

Method description

Adds a new View tab

Example code

```
CCoMPtr<ISmpPluginTab>m_SmpPluginTab
HRESULT hr = m_SmpPluginTab.CoCreateInstance(CLSID_SmpPluginTab);
m_SmpPluginTab->AddView(sLabel, pSmpPluginView, sTooltip)
```

[Back to ISmpPluginTab members](#)

ISmpPluginTab::CreateFormView

method CreateFormView

```
Sub CreateFormView(sLabel As String, sTooltip As String, pView,  
plIndex As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	sLabel	String	No	-	Label of the new tab
2	sTooltip	String	No	-	Tooltip for the new tab
3	pView	Variant	No	-	Pointer to the new tab view
4	plIndex	Long	No	-	Index of the new tab view

Method description

Creates a new form view tab

Example code

```
CCoMPtr<ISmpPluginTab>m_SmpPluginTab  
HRESULT hr = m_SmpPluginTab.CoCreateInstance(CLSID_SmpPluginTab);  
m_SmpPluginTab->CreateFormView(strLabel,strToolTip,&vTabView,&m_lInd
```

[Back to ISmpPluginTab members](#)

ISmpPluginTab::CreateView

method CreateView

```
Sub CreateView(sLabel As String, sTooltip As String, pView, plIndex  
As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	sLabel	String	No	-	Label of the new tab
2	sTooltip	String	No	-	Tooltip for the new tab
3	pView	Variant	No	-	Pointer to the new tab view
4	plIndex	Long	No	-	Index of the new tab view

Method description

Creates a new view tab

Example code

```
CCoMPtr<ISmpPluginTab>m_SmpPluginTab  
HRESULT hr = m_SmpPluginTab.CoCreateInstance(CLSID_SmpPluginTab);  
m_SmpPluginTab->CreateView(strLabel,strToolTip, &vTabView,&m_lIndex)
```

[Back to ISmpPluginTab members](#)

ISmpPluginTab::CreateWinFormsView

method CreateWinFormsView

```
Sub CreateWinFormsView(sLabel As String, sTooltip As String, pView,  
plIndex As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	sLabel	String	No	-	Label of the new tab
2	sTooltip	String	No	-	Tooltip for the new tab
3	pView	Variant	No	-	Pointer to the new tab view
4	plIndex	Long	No	-	Index of the new tab view

Method description

Create a new WinFormsView tab

Example code

```
CCoMPtr<ISmpPluginTab>m_SmpPluginTab  
HRESULT hr = m_SmpPluginTab.CoCreateInstance(CLSID_SmpPluginTab);  
m_SmpPluginTab->CreateWinFormsView(strLabel, strToolTip, &vTabView,&
```

[Back to ISmpPluginTab members](#)

ISmpPluginTab::GetWindowRect

method GetWindowRect

```
Sub GetWindowRect(lTabIndex As Long, pX As Long, pY As Long, pWidth  
As Long, pHHeight As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	lTabIndex	Long	No	-	
2	pX	Long	No	-	
3	pY	Long	No	-	
4	pWidth	Long	No	-	
5	pHeight	Long	No	-	

[Back to ISmpPluginTab members](#)

ISmpPluginTab::SetCurrentView

method SetCurrentView

```
Sub SetCurrentView(lIndex As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	lIndex	Long	No	-	Index of the tab

Method description

Sets the Curerent view to the specified tab

Example code

```
CComPtr<ISmpPluginTab>m_SmpPluginTab  
HRESULT hr = m_SmpPluginTab.CoCreateInstance(CLSID_SmpPluginTab);  
m_SmpPluginTab->SetCurrentView(lIndex)
```

[Back to ISmpPluginTab members](#)

ISmpPluginTab::WindowHandle

property WindowHandle

```
Property Get WindowHandle(iTabIndex As Long) As Variant
```

Parameters

No	Name	Type	Optional	Default	Description
1	iTabIndex	Long	No	-	

[Back to ISmpPluginTab members](#)

Coclass: CustomerEvents

Interface: ICustomerEvents

[Browse members alphabetically](#)

[Browse members by category](#)

[Browse members by use](#)

ICustomerEvents members

Properties

Name	Type	HelpString	Category	Frequency of use
OnCustomerAdd	Method	method OnCustomerAdd	General	Normal
OnCustomerDelete	Method	method OnCustomerDelete	General	Normal
OnCustomerEdit	Method	method OnCustomerEdit	General	Normal
OnShowCustomerDetails	Method	method OnShowCustomerDetails	General	Normal

[ICustomerEvents overview](#)

ICustomerEvents::OnCustomerAdd

method OnCustomerAdd

```
Sub OnCustomerAdd(strCustomerID As String)
```

Parameters

No	Name	Type	Optional	Default	Description
1	strCustomerID	String	No	-	

Method description

This method is used to add a new customer.

[Back to ICustomerEvents members](#)

ICustomerEvents::OnCustomerDelete

method OnCustomerDelete

```
Sub OnCustomerDelete(strCustomerID As String)
```

Parameters

No	Name	Type	Optional	Default	Description
1	strCustomerID	String	No	-	

Method description

This method is used to delete an existing customer details.

[Back to ICustomerEvents members](#)

ICustomerEvents::OnCustomerEdit

method OnCustomerEdit

```
Sub OnCustomerEdit(strCustomerID As String)
```

Parameters

No	Name	Type	Optional	Default	Description
1	strCustomerID	String	No	-	

Method description

This method is used to edit the details of an existing customer.

[Back to ICustomerEvents members](#)

ICustomerEvents::OnShowCustomerDetails

method OnShowCustomerDetails

```
Sub OnShowCustomerDetails(strCustID As String, varGenericReport)
```

Parameters

No	Name	Type	Optional	Default	Description
1	strCustID	String	No	-	
2	varGenericReport	Variant	No	-	

Method description

This method is used to display the details of an existing customer.

[Back to ICustomerEvents members](#)

Coclass: SmpUser

Interface: ISmpUser

[Browse members alphabetically](#)

[Browse members by category](#)

[Browse members by use](#)

ISmpUser members

Properties

Name	Type	HelpString	Category	Frequency of use
CurrentLoginUser	Property Get	property CurrentLoginUser	General	Normal
InvokeChangePasswordDlg	Method	method InvokeChangePasswordDlg	General	Normal
InvokeLoginUserDlg	Method	method InvokeLoginUserDlg	General	Normal

[ISmpUser overview](#)

ISmpUser::CurrentLoginUser

property CurrentLoginUser

```
Property Get CurrentLoginUser As String
```

No parameters

Property description

Represents the current Login User

[Back to ISmpUser members](#)

ISmpUser::InvokeChangePasswordDlg

method InvokeChangePasswordDlg

```
Sub InvokeChangePasswordDlg
```

No parameters

Method description

Invokes the change password dialog

Example code

```
CComPtr<ISmpUser>m_SmpUser  
HRESULT hr = m_SmpUser.CoCreateInstance(CLSID_SmpUser)  
m_SmpUser->InvokeChangePasswordDlg()
```

[Back to ISmpUser members](#)

ISmpUser::InvokeLoginUserDlg

method InvokeLoginUserDlg

```
Sub InvokeLoginUserDlg
```

No parameters

Method description

Invokes the login user dialog

Example code

```
CComPtr<ISmpUser>m_SmpUser  
HRESULT hr = m_SmpUser.CoCreateInstance(CLSID_SmpUser)  
m_SmpUser->InvokeLoginUserDlg()
```

[Back to ISmpUser members](#)

Coclass: SmpUserEvents

Interface: ISmpUserEvents

[Browse members alphabetically](#)

[Browse members by category](#)

[Browse members by use](#)

ISmpUserEvents members

Properties

Name	Type	HelpString	Category	Frequency of use
AddLoginUserPages	Method	method AddLoginUserPages	General	Normal
OnUserLogin	Method	method OnUserLogin	General	Normal
OnUserLogout	Method	method OnUserLogout	General	Normal

[ISmpUserEvents overview](#)

ISmpUserEvents::AddLoginUserPages

method AddLoginUserPages

```
Sub AddLoginUserPages(pSheet)
```

Parameters

No	Name	Type	Optional	Default	Description
1	pSheet	Variant	No	-	It is a VARIANT value that is used to get the login page

Method description

It is used to create a tab in the login page

Example code

```
CPropertySheet* pAddLoginUserPages=(CPropertySheet*)pSheet.byref;
CComPtr<ISmpPluginTab> SmpPluginTab;
SmpPluginTab.CoCreateInstance(CLSID_SmpPluginTab);
VARIANT Var;
Var.vt=VT_BYREF;
Var.byref=m_SMPUserEventDlg;
SmpPluginTab->AddSmpPage(Var);
return S_OK;
```

[Back to ISmpUserEvents members](#)

ISmpUserEvents::OnUserLogin

method OnUserLogin

```
Sub OnUserLogin(strUserName As String)
```

Parameters

No	Name	Type	Optional	Default	Description
1	strUserName	String	No	-	It is a BSTR that gives the User name

Method description

It is used to used show the login message box

Example code

```
CString strName;
strName=strUserName;
CString strMsg(strName);
strMsg+=_T(" Logged in");
AfxMessageBox(strMsg);
return S_OK;
```

[Back to ISmpUserEvents members](#)

ISmpUserEvents::OnUserLogout

method OnUserLogout

```
Sub OnUserLogout(strUserLoginName As String)
```

Parameters

No	Name	Type	Optional	Default	Description
1	strUserLoginName	String	No	-	It is a BSTR that gives the User name

Method description

It is used to used show the logout message box

Example code

```
CString strName;  
strName=strUserLoginName;  
CString strMsg(strName);  
strMsg+=_T(" Logged out");  
AfxMessageBox(strMsg);  
return S_OK;
```

[Back to ISmpUserEvents members](#)

Coclass: SmpPluginTabEvents

Interface: ISmpPluginTabEvents

[Browse members alphabetically](#)

[Browse members by category](#)

[Browse members by use](#)

ISmpPluginTabEvents members

Properties

Name	Type	HelpString	Category	Frequency of use
OnSetCurView	Method	method OnSetCurView	General	Normal

[ISmpPluginTabEvents overview](#)

ISmpPluginTabEvents::OnSetCurView

method OnSetCurView

```
Sub OnSetCurView(lCurViewIndex As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	lCurViewIndex	Long	No	-	

Method Description

This method is used to set the current view of the application.

[Back to ISmpPluginTabEvents members](#)

Coclass: SmpDialogExt

Interface: ISmpDialogExt

[Browse members alphabetically](#)

[Browse members by category](#)

[Browse members by use](#)

ISmpDialogExt members

Properties

Name	Type	HelpString	Category	Frequency of use
AddAboutBoxPages	Method	method AddAboutBoxPages	General	Normal
AddCustomerPages	Method	method AddCustomerPages	General	Normal
AddDeleteOldDataPages	Method	method AddDeleteOldDataPages	General	Normal
AddManageUserPages	Method	method AddManageUserPages	General	Normal
AddSetupPages	Method	method AddSetupPages	General	Normal
AddShopPages	Method	method AddShopPages	General	Normal
AddStockItemPages	Method	method AddStockItemPages	General	Normal
AddTransactionPages	Method	method AddTransactionPages	General	Normal

[ISmpDialogExt overview](#)

ISmpDialogExt::AddAboutBoxPages

method AddAboutBoxPages

```
Sub AddAboutBoxPages(pSheet)
```

Parameters

No	Name	Type	Optional	Default	Description
1	pSheet	Variant	No	-	

[Back to ISmpDialogExt members](#)

ISmpDialogExt::AddCustomerPages

method AddCustomerPages

```
Sub AddCustomerPages(pSheet)
```

Parameters

No	Name	Type	Optional	Default	Description
1	pSheet	Variant	No	-	

[Back to ISmpDialogExt members](#)

ISmpDialogExt::AddDeleteOldDataPages

method AddDeleteOldDataPages

```
Sub AddDeleteOldDataPages(pSheet)
```

Parameters

No	Name	Type	Optional	Default	Description
1	pSheet	Variant	No	-	

[Back to ISmpDialogExt members](#)

ISmpDialogExt::AddManageUserPages

method AddManageUserPages

```
Sub AddManageUserPages(pSheet)
```

Parameters

No	Name	Type	Optional	Default	Description
1	pSheet	Variant	No	-	

[Back to ISmpDialogExt members](#)

ISmpDialogExt::AddSetupPages

method AddSetupPages

```
Sub AddSetupPages(pSheet)
```

Parameters

No	Name	Type	Optional	Default	Description
1	pSheet	Variant	No	-	

[Back to ISmpDialogExt members](#)

ISmpDialogExt::AddShopPages

method AddShopPages

```
Sub AddShopPages(pSheet)
```

Parameters

No	Name	Type	Optional	Default	Description
1	pSheet	Variant	No	-	

[Back to ISmpDialogExt members](#)

ISmpDialogExt::AddStockItemPages

method AddStockItemPages

```
Sub AddStockItemPages(pSheet)
```

Parameters

No	Name	Type	Optional	Default	Description
1	pSheet	Variant	No	-	

[Back to ISmpDialogExt members](#)

ISmpDialogExt::AddTransactionPages

method AddTransactionPages

```
Sub AddTransactionPages(pSheet)
```

Parameters

No	Name	Type	Optional	Default	Description
1	pSheet	Variant	No	-	

[Back to ISmpDialogExt members](#)

Coclass: SmpReceiptSettings

Interface: ISmpReceiptSettings

[Browse members alphabetically](#)

[Browse members by category](#)

[Browse members by use](#)

ISmpReceiptSettings members

Properties

Name	Type	HelpString	Category	Frequency of use
AlwaysPrintSalesReceipt	Property Get	property AlwaysPrintSalesReceipt	General	Normal
BypassPrintDlg	Property Get	property BypassPrintDlg	General	Normal
EnableDefaultReceiptPrinter	Property Get	property EnableDefaultReceiptPrinter	General	Normal
FooterText	Property Get	property FooterText	General	Normal
PhoneNumberAtFooter	Property Get	property PhoneNumberAtFooter	General	Normal
PrintFooterText	Property Get	property PrintFooterText	General	Normal
PrintReceiptsContinuously	Property Get	property PrintReceiptsContinuously	General	Normal
PrintShopNameAtHeader	Property Get	property PrintShopNameAtHeader	General	Normal
PrintTimeAtFooter	Property Get	property PrintTimeAtFooter	General	Normal
ReceiptPrinterName	Property Get	property ReceiptPrinterName	General	Normal
ReceiptSpacing	Property Get	property ReceiptSpacing	General	Normal

[ISmpReceiptSettings](#) overview

ISmpReceiptSettings::AlwaysPrintSalesReceipt

property AlwaysPrintSalesReceipt

Property Get AlwaysPrintSalesReceipt As Long

No parameters

Property description

It is used to check whether AlwaysPrintSalesReceipt option is enabled or not

Example code

```
CComPtr<ISmpReceiptSettings>m_SmpReceiptSettings;
HRESULT hr=m_SmpReceiptSettings.CoCreateInstance(CLSID_SmpReceiptSet
if(FAILED(hr))
{
    AfxMessageBox(_T("SMPReceipt Settings Failed"));
    return FALSE;
}
long lPrntReceipt=0;
HRESULT hr=m_SmpReceiptSettings->get_AlwaysPrintSalesReceipt(&lPrntR
if(FAILED(hr))
{
    AfxMessageBox(_T("Failed to load"));
}
if(lPrntReceipt==TRUE)
{
    AfxMessageBox(_T("AlwaysPrintSalesReceipt option is Enabled"));
}
else
{
    AfxMessageBox(_T("AlwaysPrintSalesReceipt option is Disabled"));
}
```

[Back to ISmpReceiptSettings members](#)

ISmpReceiptSettings::BypassPrintDlg

property BypassPrintDlg

```
Property Get BypassPrintDlg As Long
```

No parameters

Property description

It is used to check whether BypassPrintDlg option is enabled or not

Example code

```
CComPtr<ISmpReceiptSettings>m_SmpReceiptSettings;
HRESULT hr=m_SmpReceiptSettings.CoCreateInstance(CLSID_SmpReceiptSet
if(FAILED(hr))
{
    AfxMessageBox(_T("SMPReceipt Settings Failed"));
    return FALSE;
}
long lBypassPrnt=0;
HRESULT hr=m_SmpReceiptSettings->get_BypassPrintDlg(&lBypassPrnt);
if(FAILED(hr))
{
    AfxMessageBox(_T("Failed to load"));
}
if(lBypassPrnt==TRUE)
{
    AfxMessageBox(_T("BypassPrint option is Enabled"));
}
else
{
    AfxMessageBox(_T("BypassPrint option is Disabled"));
}
```

[Back to ISmpReceiptSettings members](#)

ISmpReceiptSettings::EnableDefaultReceiptPrinter

property EnableDefaultReceiptPrinter

```
Property Get EnableDefaultReceiptPrinter As Long
```

No parameters

Property description

It is used to check whether EnableDefaultReceiptPrinter option is enabled or not

Example code

```
CComPtr<ISmpReceiptSettings>m_SmpReceiptSettings;
HRESULT hr=m_SmpReceiptSettings.CoCreateInstance(CLSID_SmpReceiptSet
if(FAILED(hr))
{
    AfxMessageBox(_T("SMPReceipt Settings Failed"));
    return FALSE;
}
long lReceiptPrntr=0;
HRESULT hr=m_SmpReceiptSettings->get_EnableDefaultReceiptPrinter(&lR
if(FAILED(hr))
{
    AfxMessageBox(_T("Failed to load"));
}
if(lReceiptPrntr==TRUE)
{
    AfxMessageBox(_T(" DefaultReceiptPrinter option is Enabled"));
}
else
{
    AfxMessageBox(_T("DefaultReceiptPrinter option is Disabled"));
}
```

[Back to ISmpReceiptSettings members](#)

ISmpReceiptSettings::FooterText

property FooterText

```
Property Get FooterText As String
```

No parameters

Property description

It is used to view the footer text

Example code

```
CComPtr<ISmpReceiptSettings>m_SmpReceiptSettings;
HRESULT hr=m_SmpReceiptSettings.CoCreateInstance(CLSID_SmpReceiptSet
if(FAILED(hr))
{
    AfxMessageBox(_T("SMPReceipt Settings Failed"));
    return FALSE;
}
BSTR bstr;
CString str;
HRESULT hr=m_SmpReceiptSettings->get_FooterText(&bstr);
if(FAILED(hr))
{
    AfxMessageBox(_T("Failed to load"));
}
str=bstr;
if(str.IsEmpty())
{
    AfxMessageBox(_T("Footer Text is not Entered"));
}
else
AfxMessageBox(str);
```

[Back to ISmpReceiptSettings members](#)

ISmpReceiptSettings::PhoneNumberAtFooter

property PhoneNumberAtFooter

Property Get PhoneNumberAtFooter As Long

No parameters

Property description

It is used to Check whether PhoneNumberAtFooter option is enabled or not

Example code

```
CComPtr<ISmpReceiptSettings>m_SmpReceiptSettings;
HRESULT hr=m_SmpReceiptSettings.CoCreateInstance(CLSID_SmpReceiptSet
if(FAILED(hr))
{
    AfxMessageBox(_T("SMPReceipt Settings Failed"));
    return FALSE;
}
long lFooterPhNo;
HRESULT hr=m_SmpReceiptSettings->get_PhoneNumberAtFooter(&lFooterPhN
if(FAILED(hr))
{
    AfxMessageBox(_T("Failed to load"));
}
if(lFooterPhNo==TRUE)
{
    AfxMessageBox(_T("""Phone Number At Footer option is enabled"""));
}
else
AfxMessageBox(_T("""Phone Number At Footer option is disabled"""));
```

[Back to ISmpReceiptSettings members](#)

ISmpReceiptSettings::PrintFooterText

property PrintFooterText

Property Get PrintFooterText As Long

No parameters

Property description

It is used to check whether PrintFooterText option is enabled or not

Example code

```
CComPtr<ISmpReceiptSettings>m_SmpReceiptSettings;
HRESULT hr=m_SmpReceiptSettings.CoCreateInstance(CLSID_SmpReceiptSet
if(FAILED(hr))
{
    AfxMessageBox(_T("SMPReceipt Settings Failed"));
    return FALSE;
}
long lPrintFooterTxt;
HRESULT hr=m_SmpReceiptSettings->get_PrintFooterText(&lPrintFooterTx
if(FAILED(hr))
{
    AfxMessageBox(_T("Failed to load"));
}
if(lPrintFooterTxt==TRUE)
{
    AfxMessageBox(_T("Print Footer Text is enabled"));
}
else
AfxMessageBox(_T("Print Footer Text is disabled"));
```

[Back to ISmpReceiptSettings members](#)

ISmpReceiptSettings::PrintReceiptsContinuously

property PrintReceiptsContinuously

```
Property Get PrintReceiptsContinuously As Long
```

No parameters

Property description

It is used to check whether PrintReceiptsContinuously option is enabled or not

Example code

```
CComPtr<ISmpReceiptSettings>m_SmpReceiptSettings;
HRESULT hr=m_SmpReceiptSettings.CoCreateInstance(CLSID_SmpReceiptSet
if(FAILED(hr))
{
    AfxMessageBox(_T("SMPReceipt Settings Failed"));
    return FALSE;
}
long lPrntReceiptCntsly;
HRESULT hr=m_SmpReceiptSettings->get_PrintReceiptsContinuously(&lPrn
if(FAILED(hr))
{
    AfxMessageBox(_T("Failed to load"));
}
if(lPrntReceiptCntsly==TRUE)
{
    AfxMessageBox(_T("Print Receipts Continuously option is enabled"))
}
else
    AfxMessageBox(_T("Print Receipts Continuously option is disabled"))
```

[Back to ISmpReceiptSettings members](#)

ISmpReceiptSettings::PrintShopNameAtHeader

property PrintShopNameAtHeader

```
Property Get PrintShopNameAtHeader As Long
```

No parameters

Property description

It is used to check whether PrintShopNameAtHeader option is enabled or not

Example code

```
CComPtr<ISmpReceiptSettings>m_SmpReceiptSettings;
HRESULT hr=m_SmpReceiptSettings.CoCreateInstance(CLSID_SmpReceiptSet
if(FAILED(hr))
{
    AfxMessageBox(_T("SMPReceipt Settings Failed"));
    return FALSE;
}
long lHeaderShpNme;
HRESULT hr=m_SmpReceiptSettings->get_PrintShopNameAtHeader(&lHeaderS
if(FAILED(hr))
{
    AfxMessageBox(_T("Failed to load"));
}
if(lHeaderShpNme==TRUE)
{
    AfxMessageBox(_T("Print ShopName At Header option is enabled"));
}
else
AfxMessageBox(_T("Print ShopName At Header option is disabled"));
```

[Back to ISmpReceiptSettings members](#)

ISmpReceiptSettings::PrintTimeAtFooter

property PrintTimeAtFooter

Property Get PrintTimeAtFooter As Long

No parameters

Property description

It is used to check whether PrintTimeAtFooter option is enabled or not

Example code

```
CComPtr<ISmpReceiptSettings>m_SmpReceiptSettings;
HRESULT hr=m_SmpReceiptSettings.CoCreateInstance(CLSID_SmpReceiptSet
if(FAILED(hr))
{
    AfxMessageBox(_T("SMPReceipt Settings Failed"));
    return FALSE;
}
long lPrntFooterTime;
HRESULT hr=m_SmpReceiptSettings->get_PrintTimeAtFooter(&lPrntFooterT
if(FAILED(hr))
{
    AfxMessageBox(_T("Failed to load"));
}
if(lPrntFooterTime==TRUE)
{
    AfxMessageBox(_T("Print Time At Footer option is enabled"));
}
else
    AfxMessageBox(_T("Print Time At Footer option is disabled"));
```

[Back to ISmpReceiptSettings members](#)

ISmpReceiptSettings::ReceiptPrinterName

property ReceiptPrinterName

```
Property Get ReceiptPrinterName As String
```

No parameters

Property description

It is used to view the Receipt printer name

Example code

```
CComPtr<ISmpReceiptSettings>m_SmpReceiptSettings;
HRESULT hr=m_SmpReceiptSettings.CoCreateInstance(CLSID_SmpReceiptSet
if(FAILED(hr))
{
    AfxMessageBox(_T("SMPReceipt Settings Failed"));
    return FALSE;
}
BSTR bstr;
CString str;
HRESULT hr=m_SmpReceiptSettings->get_ReceiptPrinterName(&bstr);
if(FAILED(hr))
{
    AfxMessageBox(_T("Failed to load"));
}
str=bstr;
if(str.IsEmpty())
{
    AfxMessageBox(_T("Printer Name is not Entered"));
}
else
    AfxMessageBox(str);
```

[Back to ISmpReceiptSettings members](#)

ISmpReceiptSettings::ReceiptSpacing

property ReceiptSpacing

```
Property Get ReceiptSpacing As Long
```

No parameters

Property description

It is used to view the spacing length given

Example code

```
CComPtr<ISmpReceiptSettings>m_SmpReceiptSettings;
HRESULT hr=m_SmpReceiptSettings.CoCreateInstance(CLSID_SmpReceiptSet
if(FAILED(hr))
{
    AfxMessageBox(_T("SMPReceipt Settings Failed"));
    return FALSE;
}
long lSpcing;
CString str;
HRESULT hr=m_SmpReceiptSettings->get_ReceiptSpacing(&lSpcing);
if(FAILED(hr))
{
    AfxMessageBox(_T("Failed to load"));
}
str.Format(_T("Spacing is %ld"),lSpcing);
AfxMessageBox(str);
```

[Back to ISmpReceiptSettings members](#)

Coclass: SmpReportSettings

Interface: ISmpReportSettings

[Browse members alphabetically](#)

[Browse members by category](#)

[Browse members by use](#)

ISmpReportSettings members

Properties

Name	Type	HelpString	Category	Frequency of use
AllwaysPrintMembershipForm	Property Get	property AllwaysPrintMembershipForm	General	Normal
BypassPrintDlg	Property Get	property BypassPrintDlg	General	Normal
PrintPhNoAtFooter	Property Get	property PrintPhNoAtFooter	General	Normal
PrintShopLogo	Property Get	property PrintShopLogo	General	Normal
PrintShopNameAtHeader	Property Get	property PrintShopNameAtHeader	General	Normal
PrintTimeAtFooter	Property Get	property PrintTimeAtFooter	General	Normal

[ISmpReportSettings overview](#)

ISmpReportSettings::AllwaysPrintMembershipForm

property AllwaysPrintMembershipForm

```
Property Get AllwaysPrintMembershipForm As Long
```

No parameters

Property description

It is used to get print membership form

Example code

```
CComPtr<ISmpReportSettings>m_objCSmpReportSettingsDlg;  
HRESULT hr=m_objCSmpReportSettingsDlg.CoCreateInstance(CLSID_SmpRepo  
long m_lValue;  
m_objCSmpReportSettingsDlg->get_AllwaysPrintMembershipForm(&m_lValue
```

[Back to ISmpReportSettings members](#)

ISmpReportSettings::BypassPrintDlg

property BypassPrintDlg

Property Get BypassPrintDlg As Long

No parameters

[Back to ISmpReportSettings members](#)

(C) 1999-2001 My Company All rights reserved

ISmpReportSettings::PrintPhNoAtFooter

property PrintPhNoAtFooter

Property Get PrintPhNoAtFooter As Long

No parameters

[Back to ISmpReportSettings members](#)

ISmpReportSettings::PrintShopLogo

property PrintShopLogo

Property Get PrintShopLogo As Long

No parameters

[Back to ISmpReportSettings members](#)

(C) 1999-2001 My Company All rights reserved

ISmpReportSettings::PrintShopNameAtHeader

property PrintShopNameAtHeader

Property Get PrintShopNameAtHeader As Long

No parameters

[Back to ISmpReportSettings members](#)

(C) 1999-2001 My Company All rights reserved

ISmpReportSettings::PrintTimeAtFooter

property PrintTimeAtFooter

Property Get PrintTimeAtFooter As Long

No parameters

[Back to ISmpReportSettings members](#)

Coclass: SmpFrame

Interface: ISmpFrame

[Browse members alphabetically](#)

[Browse members by category](#)

[Browse members by use](#)

ISmpFrame members

Properties

Name	Type	HelpString	Category	Frequency of use
LeftToolbarHandle	Property Get	property LeftToolbarHandle	General	Normal
MainFrameHandle	Property Get	property MainFrameHandle	General	Normal
MainToolbarHandle	Property Get	property MainToolbarHandle	General	Normal
MenuHandle	Property Get	property MenuHandle	General	Normal
PluginToolbarCount	Property Get	property PluginToolbarCount	General	Normal
PluginToolbarHandle	Property Get	property PluginToolbarHandle	General	Normal
RightToolbarHandle	Property Get	property RightToolbarHandle	General	Normal
SetPaneStatusText	Method	method SetPaneStatusText	General	Normal
StatusbarHandle	Property Get	property StatusbarHandle	General	Normal

[ISmpFrame overview](#)

ISmpFrame::LeftToolbarHandle

property LeftToolbarHandle

```
Property Get LeftToolbarHandle As Variant
```

No parameters

Property description

Used to get left toolbar handle

Example code

```
CComPtr<ISmpFrame>m_ISmpFrame;  
HRESULT hr = m_ISmpFrame.CoCreateInstance(CLSID_SmpFrame);  
m_ISmpFrame->get_LeftToolbarHandle(&var_val);
```

[Back to ISmpFrame members](#)

ISmpFrame::MainFrameHandle

property MainFrameHandle

```
Property Get MainFrameHandle As Variant
```

No parameters

Property description

Used to get main frame handle

Example code

```
CComPtr<ISmpFrame>m_ISmpFrame;  
HRESULT hr = m_ISmpFrame.CoCreateInstance(CLSID_SmpFrame);  
m_ISmpFrame->get_MainFrameHandle(&var_val);
```

[Back to ISmpFrame members](#)

ISmpFrame::MainToolbarHandle

property MainToolbarHandle

```
Property Get MainToolbarHandle As Variant
```

No parameters

Property description

used to get main toolbar handle

Example code

```
CComPtr<ISmpFrame>m_ISmpFrame;  
HRESULT hr = m_ISmpFrame.CoCreateInstance(CLSID_SmpFrame);  
m_ISmpFrame->get_MainToolbarHandle(&var_val);
```

[Back to ISmpFrame members](#)

ISmpFrame::MenuHandle

property MenuHandle

```
Property Get MenuHandle As Variant
```

No parameters

Property description

used to get menu handle

Example code

```
CComPtr<ISmpFrame>m_ISmpFrame;  
HRESULT hr = m_ISmpFrame.CoCreateInstance(CLSID_SmpFrame);  
m_ISmpFrame->get_MenuHandle(&var_val);
```

[Back to ISmpFrame members](#)

ISmpFrame::PluginToolbarCount

property PluginToolbarCount

```
Property Get PluginToolbarCount As Long
```

No parameters

Property description

used to get plugin toolbar count

Example code

```
CComPtr<ISmpFrame>m_ISmpFrame;  
HRESULT hr = m_ISmpFrame.CoCreateInstance(CLSID_SmpFrame);  
m_ISmpFrame->get_PluginToolbarCount(&lval);
```

[Back to ISmpFrame members](#)

ISmpFrame::PluginToolbarHandle

property PluginToolbarHandle

```
Property Get PluginToolbarHandle(lIndex As Long) As Variant
```

Parameters

No	Name	Type	Optional	Default	Description
1	lIndex	Long	No	-	

Property description

used to get plugin toolbar handle

Example code

```
CComPtr<ISmpFrame>m_ISmpFrame;  
HRESULT hr = m_ISmpFrame.CoCreateInstance(CLSID_SmpFrame);  
m_ISmpFrame->get_PluginToolbarHandle(lval,&var_val);
```

[Back to ISmpFrame members](#)

ISmpFrame::RightToolbarHandle

property RightToolbarHandle

```
Property Get RightToolbarHandle As Variant
```

No parameters

Property description

used to get right toolbar handle

Example code

```
CComPtr<ISmpFrame>m_ISmpFrame;  
HRESULT hr = m_ISmpFrame.CoCreateInstance(CLSID_SmpFrame);  
m_ISmpFrame->get_RightToolbarHandle(&var_val);
```

[Back to ISmpFrame members](#)

ISmpFrame::SetPaneStatusText

method SetPaneStatusText

```
Sub SetPaneStatusText(lPane As Long, strStatusText As String,  
lColor As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	lPane	Long	No	-	
2	strStatusText	String	No	-	
3	lColor	Long	No	-	

Method description

used to set pane status text

Example code

```
CComPtr<ISmpFrame>m_ISmpFrame;  
HRESULT hr = m_ISmpFrame.CoCreateInstance(CLSID_SmpFrame);  
m_ISmpFrame->SetPaneStatusText(lval,bstr_statustext,(COLORREF)RGB(ir
```

[Back to ISmpFrame members](#)

ISmpFrame::StatusbarHandle

property StatusbarHandle

```
Property Get StatusbarHandle As Variant
```

No parameters

Property description

used to get status bar handle

Example code

```
CComPtr<ISmpFrame>m_ISmpFrame;  
HRESULT hr = m_ISmpFrame.CoCreateInstance(CLSID_SmpFrame);  
m_ISmpFrame->get_StatusbarHandle(&var_val);
```

[Back to ISmpFrame members](#)

Coclass: SmpReportItemAttributes

Interface: ISmpReportItemAttributes

[Browse members alphabetically](#)

[Browse members by category](#)

[Browse members by use](#)

ISmpReportItemAttributes members

Properties

Name	Type	HelpString	Category	Frequency of use
BackgroundColor	Property Get/Let	property BackgroundColor	General	Normal
FooterBold	Property Get/Let	property FooterBold	General	Normal
FooterFont	Property Get/Let	property FooterFont	General	Normal
FooterFontSize	Property Get/Let	property FooterFontSize	General	Normal
FooterItalic	Property Get/Let	property FooterItalic	General	Normal
ForegroundColor	Property Get/Let	property ForegroundColor	General	Normal
GetMarginInfo	Method	method GetMarginInfo	General	Normal
HeadingBold	Property Get/Let	property HeadingBold	General	Normal
HeadingFont	Property Get/Let	property HeadingFont	General	Normal
HeadingFontSize	Property Get/Let	property HeadingFontSize	General	Normal
HeadingItalics	Property Get/Let	property HeadingItalics	General	Normal
ImageColumnPosition	Property Get/Let	property ImageColumnPosition	General	Normal
ImagePath	Property Get/Let	property ImagePath	General	Normal
ImageRowPosition	Property Get/Let	property ImageRowPosition	General	Normal
Item	Property Get/Let	property Item	General	Normal
ItemCount	Property Get/Let	property ItemCount	General	Normal
NormalBold	Property Get/Let	property NormalBold	General	Normal
NormalFont	Property Get/Let	property NormalFont	General	Normal
NormalFontSize	Property Get/Let	property NormalFontSize	General	Normal
NormalItalic	Property Get/Let	property NormalItalic	General	Normal
SetMarginInfo	Method	method SetMarginInfo	General	Normal
ShowHeading	Property Get/Let	property ShowHeading	General	Normal
ShowImage	Property Get/Let	property ShowImage	General	Normal

[ISmpReportItemAttributes overview](#)

ISmpReportItemAttributes::BackgroundColor

property BackgroundColor

Property Get/Let BackgroundColor As Long

No parameters

[Back to ISmpReportItemAttributes members](#)

(C) 1999-2001 My Company All rights reserved

ISmpReportItemAttributes::FooterBold

property FooterBold

Property Get/Let FooterBold As Long

No parameters

[Back to ISmpReportItemAttributes members](#)

(C) 1999-2001 My Company All rights reserved

ISmpReportItemAttributes::FooterFont

property FooterFont

Property Get/Let FooterFont As String

No parameters

[Back to ISmpReportItemAttributes members](#)

(C) 1999-2001 My Company All rights reserved

ISmpReportItemAttributes::FooterFontSize

property FooterFontSize

Property Get/Let FooterFontSize As Long

No parameters

[Back to ISmpReportItemAttributes members](#)

ISmpReportItemAttributes::FooterItalic

property FooterItalic

Property Get/Let FooterItalic As Long

No parameters

[Back to ISmpReportItemAttributes members](#)

(C) 1999-2001 My Company All rights reserved

ISmpReportItemAttributes::ForegroundColor

property ForegroundColor

Property Get/Let ForegroundColor As Long

No parameters

[Back to ISmpReportItemAttributes members](#)

(C) 1999-2001 My Company All rights reserved

ISmpReportItemAttributes::GetMarginInfo

method GetMarginInfo

```
Sub GetMarginInfo(lLeft As Long, lRight As Long, lTop As Long,  
lBottom As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	lLeft	Long	No	-	
2	lRight	Long	No	-	
3	lTop	Long	No	-	
4	lBottom	Long	No	-	

[Back to ISmpReportItemAttributes members](#)

ISmpReportItemAttributes::HeadingBold

property HeadingBold

Property Get/Let HeadingBold As Long

No parameters

[Back to ISmpReportItemAttributes members](#)

(C) 1999-2001 My Company All rights reserved

ISmpReportItemAttributes::HeadingFont

property HeadingFont

Property Get/Let HeadingFont As String

No parameters

[Back to ISmpReportItemAttributes members](#)

(C) 1999-2001 My Company All rights reserved

ISmpReportItemAttributes::HeadingFontSize

property HeadingFontSize

Property Get/Let HeadingFontSize As Long

No parameters

[Back to ISmpReportItemAttributes members](#)

ISmpReportItemAttributes::HeadingItalics

property HeadingItalics

Property Get/Let HeadingItalics As Long

No parameters

[Back to ISmpReportItemAttributes members](#)

(C) 1999-2001 My Company All rights reserved

ISmpReportItemAttributes::ImageColumnPosition

property ImageColumnPosition

Property Get/Let ImageColumnPosition As Long

No parameters

[Back to ISmpReportItemAttributes members](#)

ISmpReportItemAttributes::ImagePath

property ImagePath

Property Get/Let ImagePath As String

No parameters

[Back to ISmpReportItemAttributes members](#)

(C) 1999-2001 My Company All rights reserved

ISmpReportItemAttributes::ImageRowPosition

property ImageRowPosition

Property Get/Let ImageRowPosition As Long

No parameters

[Back to ISmpReportItemAttributes members](#)

(C) 1999-2001 My Company All rights reserved

ISmpReportItemAttributes::Item

property Item

```
Property Get/Let Item(lArrayIndex As Long) As IItem
```

Parameters

No	Name	Type	Optional	Default	Description
1	lArrayIndex	Long	No	-	

[Back to ISmpReportItemAttributes members](#)

ISmpReportItemAttributes::ItemCount

property ItemCount

Property Get/Let ItemCount As Long

No parameters

[Back to ISmpReportItemAttributes members](#)

(C) 1999-2001 My Company All rights reserved

ISmpReportItemAttributes::NormalBold

property NormalBold

Property Get/Let NormalBold As Long

No parameters

[Back to ISmpReportItemAttributes members](#)

(C) 1999-2001 My Company All rights reserved

ISmpReportItemAttributes::NormalFont

property NormalFont

Property Get/Let NormalFont As String

No parameters

[Back to ISmpReportItemAttributes members](#)

ISmpReportItemAttributes::NormalFontSize

property NormalFontSize

Property Get/Let NormalFontSize As Long

No parameters

[Back to ISmpReportItemAttributes members](#)

(C) 1999-2001 My Company All rights reserved

ISmpReportItemAttributes::NormalItalic

property NormalItalic

Property Get/Let NormalItalic As Long

No parameters

[Back to ISmpReportItemAttributes members](#)

(C) 1999-2001 My Company All rights reserved

ISmpReportItemAttributes::SetMarginInfo

method SetMarginInfo

```
Sub SetMarginInfo(lLeft As Long, lRight As Long, lTop As Long,  
lBottom As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	lLeft	Long	No	-	
2	lRight	Long	No	-	
3	lTop	Long	No	-	
4	lBottom	Long	No	-	

[Back to ISmpReportItemAttributes members](#)

ISmpReportItemAttributes::ShowHeading

property ShowHeading

Property Get/Let ShowHeading As Long

No parameters

[Back to ISmpReportItemAttributes members](#)

(C) 1999-2001 My Company All rights reserved

ISmpReportItemAttributes::ShowImage

property ShowImage

Property Get/Let ShowImage As Long

No parameters

[Back to ISmpReportItemAttributes members](#)

(C) 1999-2001 My Company All rights reserved

Coclass: SmpStock

Interface: ISmpStock

[Browse members alphabetically](#)

[Browse members by category](#)

[Browse members by use](#)

ISmpStock members

Properties

Name	Type	HelpString	Category	Frequency of use
InvokeAddNewStockDlg	Method	method InvokeAddNewStockDlg	General	Normal
InvokeCancelSalesDlg	Method	method InvokeCancelSalesDlg	General	Normal
InvokeCheckoutDlg	Method	method InvokeCheckoutDlg	General	Normal
InvokeEditStockDlg	Method	method InvokeEditStockDlg	General	Normal
InvokeModifyStockItemPriceDlg	Method	method InvokeModifyStockItemPriceDlg	General	Normal
InvokeStockRateSettingsDlg	Method	method InvokeStockRateSettingsDlg	General	Normal
ItemCount	Property Get	property ItemCount	General	Normal
ItemName	Property Get	property ItemName	General	Normal
StdSellingPricePerUnit	Property Get	property StdSellingPricePerUnit	General	Normal

[ISmpStock overview](#)

ISmpStock::InvokeAddNewStockDlg

method InvokeAddNewStockDlg

```
Sub InvokeAddNewStockDlg
```

No parameters

Method description

Invokes Add new Stock dialog

Example code

```
CComPtr<ISmpStock>m_SmpStock  
HRESULT hr = m_SmpStock.CoCreateInstance(CLSID_SmpStock)  
m_SmpStock->InvokeAddNewStockDlg()
```

[Back to ISmpStock members](#)

ISmpStock::InvokeCancelSalesDlg

method InvokeCancelSalesDlg

```
Sub InvokeCancelSalesDlg(pSalesID As Long)
```

Parameters

No	Name	Type	Optional	Default	Description
1	pSalesID	Long	No	-	Represents the sales ID

Method description

Invokes cancel sales dialog

Example code

```
CComPtr<ISmpStock>m_SmpStock  
HRESULT hr = m_SmpStock.CoCreateInstance(CLSID_SmpStock)  
m_SmpStock->InvokeCancelSalesDlg(&SalesID)
```

[Back to ISmpStock members](#)

ISmpStock::InvokeCheckoutDlg

method InvokeCheckoutDlg

```
Sub InvokeCheckoutDlg
```

No parameters

Method description

Invokes checkout dialog

Example code

```
CComPtr<ISmpStock>m_SmpStock  
HRESULT hr = m_SmpStock.CoCreateInstance(CLSID_SmpStock)  
m_SmpStock->InvokeCheckoutDlg()
```

[Back to ISmpStock members](#)

ISmpStock::InvokeEditStockDlg

method InvokeEditStockDlg

```
Sub InvokeEditStockDlg
```

No parameters

Method description

Invokes edit stock dialog

Example code

```
CComPtr<ISmpStock>m_SmpStock  
HRESULT hr = m_SmpStock.CoCreateInstance(CLSID_SmpStock)  
m_SmpStock->InvokeEditStockDlg()
```

[Back to ISmpStock members](#)

ISmpStock::InvokeModifyStockItemPriceDlg

method InvokeModifyStockItemPriceDlg

```
Sub InvokeModifyStockItemPriceDlg
```

No parameters

Method description

Invokes modify stock item price dialog

Example code

```
CComPtr<ISmpStock>m_SmpStock  
HRESULT hr = m_SmpStock.CoCreateInstance(CLSID_SmpStock)  
m_SmpStock->InvokeModifyStockItemPriceDlg()
```

[Back to ISmpStock members](#)

ISmpStock::InvokeStockRateSettingsDlg

method InvokeStockRateSettingsDlg

```
Sub InvokeStockRateSettingsDlg
```

No parameters

Method description

Invokes stock rate settings dialog

Example code

```
CComPtr<ISmpStock>m_SmpStock  
HRESULT hr = m_SmpStock.CoCreateInstance(CLSID_SmpStock)  
m_SmpStock->InvokeStockRateSettingsDlg()
```

[Back to ISmpStock members](#)

ISmpStock::ItemCount

property ItemCount

```
Property Get ItemCount(strItemID As String) As Long
```

Parameters

No	Name	Type	Optional	Default	Description
1	strItemID	String	No	-	Represents the Item ID

Property description

Represents the total item count

[Back to ISmpStock members](#)

ISmpStock::ItemName

property ItemName

```
Property Get ItemName(strItemID As String) As String
```

Parameters

No	Name	Type	Optional	Default	Description
1	strItemID	String	No	-	Represents the Item ID

Property description

Represents the name of the item

[Back to ISmpStock members](#)

ISmpStock::StdSellingPricePerUnit

property StdSellingPricePerUnit

```
Property Get StdSellingPricePerUnit(strItemID As String) As Double
```

Parameters

No	Name	Type	Optional	Default	Description
1	strItemID	String	No	-	Represents the Item ID

Property description

Represents the selling price for each unit

[Back to ISmpStock members](#)

Coclass: SmpStockEvents

Interface: ISmpStockEvents

[Browse members alphabetically](#)

[Browse members by category](#)

[Browse members by use](#)

ISmpStockEvents members

Properties

Name	Type	HelpString	Category	Frequency of use
AddStockItemPages	Method	method AddStockItemPages	General	Normal
OnAddStockItem	Method	method OnAddStockItem	General	Normal
OnDeleteStockItem	Method	method OnDeleteStockItem	General	Normal
OnEditStockItem	Method	method OnEditStockItem	General	Normal

[ISmpStockEvents](#) overview

ISmpStockEvents::AddStockItemPages

method AddStockItemPages

```
Sub AddStockItemPages(pSheet)
```

Parameters

No	Name	Type	Optional	Default	Description
1	pSheet	Variant	No	-	

[Back to ISmpStockEvents members](#)

ISmpStockEvents::OnAddStockItem

method OnAddStockItem

```
Sub OnAddStockItem(strItemID As String)
```

Parameters

No	Name	Type	Optional	Default	Description
1	strItemID	String	No	-	

[Back to ISmpStockEvents members](#)

ISmpStockEvents::OnDeleteStockItem

method OnDeleteStockItem

```
Sub OnDeleteStockItem(strItemID As String)
```

Parameters

No	Name	Type	Optional	Default	Description
1	strItemID	String	No	-	

[Back to ISmpStockEvents members](#)

ISmpStockEvents::OnEditStockItem

method OnEditStockItem

```
Sub OnEditStockItem(strItemID As String)
```

Parameters

No	Name	Type	Optional	Default	Description
1	strItemID	String	No	-	

[Back to ISmpStockEvents members](#)

Coclass: SmpSetup

Interface: ISmpSetup

[Browse members alphabetically](#)

[Browse members by category](#)

[Browse members by use](#)

ISmpSetup members

Properties

Name	Type	HelpString	Category	Frequency of use
InvokeCategoryMasterDlg	Method	method InvokeCategoryMasterDlg	General	Normal
InvokeCurrencySettingsDlg	Method	method InvokeCurrencySettingsDlg	General	Normal
InvokeDefaultSettingsDlg	Method	method InvokeDefaultSettingsDlg	General	Normal
InvokeDefaultSettingsExtDlg	Method	method InvokeDefaultSettingsExtDlg	General	Normal
InvokeDeleteOldDataDlg	Method	method InvokeDeleteOldDataDlg	General	Normal
InvokeManageUsersDlg	Method	method InvokeManageUsersDlg	General	Normal
InvokeMethodOfPaymentDlg	Method	method InvokeMethodOfPaymentDlg	General	Normal
InvokeMiscItemMasterDlg	Method	method InvokeMiscItemMasterDlg	General	Normal
InvokeServiceMasterDlg	Method	method InvokeServiceMasterDlg	General	Normal
InvokeSetupWizard	Method	method InvokeSetupWizard	General	Normal
InvokeShopInfoDlg	Method	method InvokeShopInfoDlg	General	Normal
InvokeStockMasterDlg	Method	method InvokeStockMasterDlg	General	Normal

[ISmpSetup overview](#)

ISmpSetup::InvokeCategoryMasterDlg

method InvokeCategoryMasterDlg

```
Sub InvokeCategoryMasterDlg
```

No parameters

Method description

Invokes the category master dialog

Example code

```
CComPtr<ISmpSetup>m_SmpSetup  
HRESULT hr= m_SmpSetup.CoCreateInstance(CLSID_SmpSetup)  
m_SmpSetup->InvokeCategoryMasterDlg()
```

[Back to ISmpSetup members](#)

ISmpSetup::InvokeCurrencySettingsDlg

method InvokeCurrencySettingsDlg

```
Sub InvokeCurrencySettingsDlg
```

No parameters

Method description

Invokes the currency settings dialog

Example code

```
CComPtr<ISmpSetup>m_SmpSetup  
HRESULT hr= m_SmpSetup.CoCreateInstance(CLSID_SmpSetup)  
m_SmpSetup->InvokeCurrencySettingsDlg()
```

[Back to ISmpSetup members](#)

ISmpSetup::InvokeDefaultSettingsDlg

method InvokeDefaultSettingsDlg

```
Sub InvokeDefaultSettingsDlg
```

No parameters

Method description

Invokes the default settings dialog

Example code

```
CComPtr<ISmpSetup>m_SmpSetup  
HRESULT hr= m_SmpSetup.CoCreateInstance(CLSID_SmpSetup)  
m_SmpSetup->InvokeDefaultSettingsDlg()
```

[Back to ISmpSetup members](#)

ISmpSetup::InvokeDefaultSettingsExtDlg

method InvokeDefaultSettingsExtDlg

```
Sub InvokeDefaultSettingsExtDlg
```

No parameters

Method description

invokes the default settingsExt dialog

Example code

```
CComPtr<ISmpSetup>m_SmpSetup  
HRESULT hr= m_SmpSetup.CoCreateInstance(CLSID_SmpSetup)  
m_SmpSetup->InvokeDefaultSettingsExtDlg()
```

[Back to ISmpSetup members](#)

ISmpSetup::InvokeDeleteOldDataDlg

method InvokeDeleteOldDataDlg

```
Sub InvokeDeleteOldDataDlg
```

No parameters

Method description

Invokes the delete old data dialog

Example code

```
CComPtr<ISmpSetup>m_SmpSetup  
HRESULT hr= m_SmpSetup.CoCreateInstance(CLSID_SmpSetup)  
m_SmpSetup->InvokeDeleteOldDataDlg()
```

[Back to ISmpSetup members](#)

ISmpSetup::InvokeManageUsersDlg

method InvokeManageUsersDlg

```
Sub InvokeManageUsersDlg
```

No parameters

Method description

Invokes manage users dialog

Example code

```
CComPtr<ISmpSetup>m_SmpSetup  
HRESULT hr= m_SmpSetup.CoCreateInstance(CLSID_SmpSetup)  
m_SmpSetup->InvokeManageUsersDlg()
```

[Back to ISmpSetup members](#)

ISmpSetup::InvokeMethodOfPaymentDlg

method InvokeMethodOfPaymentDlg

```
Sub InvokeMethodOfPaymentDlg
```

No parameters

Method description

Invokes method of payment dialog

Example code

```
CComPtr<ISmpSetup>m_SmpSetup  
HRESULT hr= m_SmpSetup.CoCreateInstance(CLSID_SmpSetup)  
m_SmpSetup->InvokeMethodOfPaymentDlg()
```

[Back to ISmpSetup members](#)

ISmpSetup::InvokeMiscItemMasterDlg

method InvokeMiscItemMasterDlg

```
Sub InvokeMiscItemMasterDlg
```

No parameters

Method description

Invokes misc Item master dialog

Example code

```
CComPtr<ISmpSetup>m_SmpSetup  
HRESULT hr= m_SmpSetup.CoCreateInstance(CLSID_SmpSetup)  
m_SmpSetup->InvokeMiscItemMasterDlg()
```

[Back to ISmpSetup members](#)

ISmpSetup::InvokeServiceMasterDlg

method InvokeServiceMasterDlg

```
Sub InvokeServiceMasterDlg
```

No parameters

Method description

Invokes service master dialog

Example code

```
CComPtr<ISmpSetup>m_SmpSetup  
HRESULT hr= m_SmpSetup.CoCreateInstance(CLSID_SmpSetup)  
m_SmpSetup->InvokeServiceMasterDlg()
```

[Back to ISmpSetup members](#)

ISmpSetup::InvokeSetupWizard

method InvokeSetupWizard

```
Sub InvokeSetupWizard
```

No parameters

Method description

Invokes setup wizard dialog

Example code

```
CComPtr<ISmpSetup>m_SmpSetup  
HRESULT hr= m_SmpSetup.CoCreateInstance(CLSID_SmpSetup)  
m_SmpSetup->InvokeSetupWizard()
```

[Back to ISmpSetup members](#)

ISmpSetup::InvokeShopInfoDlg

method InvokeShopInfoDlg

```
Sub InvokeShopInfoDlg
```

No parameters

Method description

Invokes shop info dialog

Example code

```
CComPtr<ISmpSetup>m_SmpSetup  
HRESULT hr= m_SmpSetup.CoCreateInstance(CLSID_SmpSetup)  
m_SmpSetup->InvokeShopInfoDlg()
```

[Back to ISmpSetup members](#)

ISmpSetup::InvokeStockMasterDlg

method InvokeStockMasterDlg

```
Sub InvokeStockMasterDlg
```

No parameters

Method description

Invokes stock master dialog

Example code

```
CComPtr<ISmpSetup>m_SmpSetup  
HRESULT hr= m_SmpSetup.CoCreateInstance(CLSID_SmpSetup)  
m_SmpSetup->InvokeStockMasterDlg()
```

[Back to ISmpSetup members](#)

Coclass: SmpSetupEvents

Interface: ISmpSetupEvents

[Browse members alphabetically](#)

[Browse members by category](#)

[Browse members by use](#)

ISmpSetupEvents members

Properties

Name	Type	HelpString	Category	Frequency of use
OnPluginInvokeSetupWizard	Method	method OnPluginInvokeSetupWizard	General	Normal
OnSaveDefaultSettings	Method	method OnSaveDefaultSettings	General	Normal

[ISmpSetupEvents](#) overview

ISmpSetupEvents::OnPluginInvokeSetupWizard

method OnPluginInvokeSetupWizard

```
Sub OnPluginInvokeSetupWizard
```

No parameters

[Back to ISmpSetupEvents members](#)

ISmpSetupEvents::OnSaveDefaultSettings

method OnSaveDefaultSettings

```
Sub OnSaveDefaultSettings
```

No parameters

[Back to ISmpSetupEvents members](#)

Coclass: SmpFileMenuOperations

Interface: ISmpFileMenuOperations

[Browse members alphabetically](#)

[Browse members by category](#)

[Browse members by use](#)

ISmpFileMenuOperations members

Properties

Name	Type	HelpString	Category	Frequency of use
InvokeBackupDataDlg	Method	method InvokeBackupDataDlg	General	Normal
InvokeChangePasswordDlg	Method	method InvokeChangePasswordDlg	General	Normal
InvokeExit	Method	method InvokeExit	General	Normal
InvokeExportReportDlg	Method	method InvokeExportReportDlg	General	Normal
InvokeLoginDlg	Method	method InvokeLoginDlg	General	Normal
InvokeLogout	Method	method InvokeLogout	General	Normal
InvokePrintDlg	Method	method InvokePrintDlg	General	Normal
InvokePrintOldReceiptDlg	Method	method InvokePrintOldReceiptDlg	General	Normal
InvokePrintPreviewDlg	Method	method InvokePrintPreviewDlg	General	Normal
InvokePrintSetupDlg	Method	method InvokePrintSetupDlg	General	Normal
InvokeRestoreDataDlg	Method	method InvokeRestoreDataDlg	General	Normal

[ISmpFileMenuOperations](#) overview

ISmpFileMenuOperations::InvokeBackupDataDlg

method InvokeBackupDataDlg

```
Sub InvokeBackupDataDlg
```

No parameters

Method description

Used to invoke Backup data dialog

Example code

```
CComPtr<ISmpFileMenuOperations>m_ISmpFileMenuOperations;  
HRESULT hr = m_ISmpFileMenuOperations.CoCreateInstance(CLSID_SmpFile
```

[Back to ISmpFileMenuOperations members](#)

ISmpFileMenuOperations::InvokeChangePasswordDlg

method InvokeChangePasswordDlg

```
Sub InvokeChangePasswordDlg
```

No parameters

Method description

Used to invoke Change Password dialog

Example code

```
CComPtr<ISmpFileMenuOperations>m_ISmpFileMenuOperations;  
HRESULT hr = m_ISmpFileMenuOperations.CoCreateInstance(CLSID_SmpFile
```

[Back to ISmpFileMenuOperations members](#)

ISmpFileMenuOperations::InvokeExit

method InvokeExit

```
Sub InvokeExit
```

No parameters

Method description

Used to invoke Exit dialog

Example code

```
CComPtr<ISmpFileMenuOperations>m_ISmpFileMenuOperations;  
HRESULT hr = m_ISmpFileMenuOperations.CoCreateInstance(CLSID_SmpFile
```

[Back to ISmpFileMenuOperations members](#)

ISmpFileMenuOperations::InvokeExportReportDlg

method InvokeExportReportDlg

```
Sub InvokeExportReportDlg
```

No parameters

Method description

Used to invoke Export Report dialog

Example code

```
CComPtr<ISmpFileMenuOperations>m_ISmpFileMenuOperations;  
HRESULT hr = m_ISmpFileMenuOperations.CoCreateInstance(CLSID_SmpFile
```

[Back to ISmpFileMenuOperations members](#)

ISmpFileMenuOperations::InvokeLoginDlg

method InvokeLoginDlg

```
Sub InvokeLoginDlg
```

No parameters

Method description

Used to invoke login dialog

Example code

```
CComPtr<ISmpFileMenuOperations>m_ISmpFileMenuOperations;  
HRESULT hr = m_ISmpFileMenuOperations.CoCreateInstance(CLSID_SmpFile
```

[Back to ISmpFileMenuOperations members](#)

ISmpFileMenuOperations::InvokeLogout

method InvokeLogout

```
Sub InvokeLogout
```

No parameters

Method description

Used to invoke logout dialog

Example code

```
CComPtr<ISmpFileMenuOperations>m_ISmpFileMenuOperations;  
HRESULT hr = m_ISmpFileMenuOperations.CoCreateInstance(CLSID_SmpFile
```

[Back to ISmpFileMenuOperations members](#)

ISmpFileMenuOperations::InvokePrintDlg

method InvokePrintDlg

```
Sub InvokePrintDlg
```

No parameters

Method description

Used to invoke print dialog

Example code

```
CComPtr<ISmpFileMenuOperations>m_ISmpFileMenuOperations;  
HRESULT hr = m_ISmpFileMenuOperations.CoCreateInstance(CLSID_SmpFile
```

[Back to ISmpFileMenuOperations members](#)

ISmpFileMenuOperations::InvokePrintOldReceiptDlg

method InvokePrintOldReceiptDlg

```
Sub InvokePrintOldReceiptDlg
```

No parameters

Method description

Used to invoke Print old receipt dialog

Example code

```
CComPtr<ISmpFileMenuOperations>m_ISmpFileMenuOperations;  
HRESULT hr = m_ISmpFileMenuOperations.CoCreateInstance(CLSID_SmpFile
```

[Back to ISmpFileMenuOperations members](#)

ISmpFileMenuOperations::InvokePrintPreviewDlg

method InvokePrintPreviewDlg

```
Sub InvokePrintPreviewDlg
```

No parameters

Method description

Used to invoke Print preview dialog

Example code

```
CComPtr<ISmpFileMenuOperations>m_ISmpFileMenuOperations;  
HRESULT hr = m_ISmpFileMenuOperations.CoCreateInstance(CLSID_SmpFile
```

[Back to ISmpFileMenuOperations members](#)

ISmpFileMenuOperations::InvokePrintSetupDlg

method InvokePrintSetupDlg

```
Sub InvokePrintSetupDlg
```

No parameters

Method description

Used to invoke Print setup dialog

Example code

```
CComPtr<ISmpFileMenuOperations>m_ISmpFileMenuOperations;  
HRESULT hr = m_ISmpFileMenuOperations.CoCreateInstance(CLSID_SmpFil
```

[Back to ISmpFileMenuOperations members](#)

ISmpFileMenuOperations::InvokeRestoreDataDlg

method InvokeRestoreDataDlg

```
Sub InvokeRestoreDataDlg
```

No parameters

Method description

Used to invoke Restore data dialog

Example code

```
CComPtr<ISmpFileMenuOperations>m_ISmpFileMenuOperations;  
HRESULT hr = m_ISmpFileMenuOperations.CoCreateInstance(CLSID_SmpFile
```

[Back to ISmpFileMenuOperations members](#)

Coclass: SmpHelp

Interface: ISmpHelp

[Browse members alphabetically](#)

[Browse members by category](#)

[Browse members by use](#)

ISmpHelp members

Properties

Name	Type	HelpString	Category	Frequency of use
HelpFilePath	Property Get	property HelpFilePath	General	Normal
InvokeAboutBoxDlg	Method	method InvokeAboutBoxDlg	General	Normal
InvokeHelpTopics	Method	method InvokeHelpTopics	General	Normal
InvokeMenuShortcutKeyDlg	Method	method InvokeMenuShortcutKeyDlg	General	Normal
InvokeRegisterDlg	Method	method InvokeRegisterDlg	General	Normal
InvokeTipOfTheDayDlg	Method	method InvokeTipOfTheDayDlg	General	Normal

[ISmpHelp overview](#)

ISmpHelp::HelpFilePath

property HelpFilePath

```
Property Get HelpFilePath As String
```

No parameters

Property description

Represents the Location of help file

Example code

```
get_HelpFilePath(&File_Path );
```

[Back to ISmpHelp members](#)

ISmpHelp::InvokeAboutBoxDlg

method InvokeAboutBoxDlg

```
Sub InvokeAboutBoxDlg
```

No parameters

Method description

Invokes the About Dialog

Example code

```
CComPtr<ISmpHelp>m_SMPHelp;  
HRESULT hr = m_SMPHelp.CoCreateInstance(CLSID_SmpHelp);  
m_SMPHelp-> InvokeAboutBoxDlg()
```

[Back to ISmpHelp members](#)

ISmpHelp::InvokeHelpTopics

method InvokeHelpTopics

```
Sub InvokeHelpTopics(strTopicPath As String)
```

Parameters

No	Name	Type	Optional	Default	Description
1	strTopicPath	String	No	-	Represents the path of the help file

Method description

Invokes the Help Dialog

Example code

```
CComPtr<ISmpHelp>m_SMPHelp;  
HRESULT hr = m_SMPHelp.CoCreateInstance(CLSID_SmpHelp);  
m_SMPHelp ->InvokeHelpTopics(Help File Path)
```

[Back to ISmpHelp members](#)

ISmpHelp::InvokeMenuShortcutKeyDlg

method InvokeMenuShortcutKeyDlg

```
Sub InvokeMenuShortcutKeyDlg
```

No parameters

Method description

Invokes the dialog showing Menu shortcut Keys

Example code

```
CComPtr<ISmpHelp>m_SMPHelp;  
HRESULT hr = m_SMPHelp.CoCreateInstance(CLSID_SmpHelp);  
m_SMPHelp->InvokeMenuShortcutKeyDlg()
```

[Back to ISmpHelp members](#)

ISmpHelp::InvokeRegisterDlg

method InvokeRegisterDlg

```
Sub InvokeRegisterDlg
```

No parameters

Method description

Invokes the registration dialog

Example code

```
CComPtr<ISmpHelp>m_SMPHelp;  
HRESULT hr = m_SMPHelp.CoCreateInstance(CLSID_SmpHelp);  
m_SMPHelp->InvokeRegisterDlg()
```

[Back to ISmpHelp members](#)

ISmpHelp::InvokeTipOfTheDayDlg

method InvokeTipOfTheDayDlg

```
Sub InvokeTipOfTheDayDlg
```

No parameters

Method description

Invokes the tip of the day dialog

Example code

```
CComPtr<ISmpHelp>m_SMPHelp;  
HRESULT hr = m_SMPHelp.CoCreateInstance(CLSID_SmpHelp);  
m_SMPHelp->InvokeTipOfTheDayDlg()
```

[Back to ISmpHelp members](#)

Coclass: SmpReportMenu

Interface: ISmpReportMenu

[Browse members alphabetically](#)

[Browse members by category](#)

[Browse members by use](#)

ISmpReportMenu members

Properties

Name	Type	HelpString	Category	Frequency of use
InvokeAnualAccountDlg	Method	method InvokeAnualAccountDlg	General	Normal
InvokeAnualStatisticsDlg	Method	method InvokeAnualStatisticsDlg	General	Normal
InvokeCanceledSalesDlg	Method	method InvokeCanceledSalesDlg	General	Normal
InvokeCanceledTransactionsDlg	Method	method InvokeCanceledTransactionsDlg	General	Normal
InvokeCustomerBalanceAmountDlg	Method	method InvokeCustomerBalanceAmountDlg	General	Normal
InvokeCustomerInactiveDlg	Method	method InvokeCustomerInactiveDlg	General	Normal
InvokeCustomerListDlg	Method	method InvokeCustomerListDlg	General	Normal
InvokeCustomerMostActiveDlg	Method	method InvokeCustomerMostActiveDlg	General	Normal
InvokeCustomerPaymentDetailsdlg	Method	method InvokeCustomerPaymentDetailsdlg	General	Normal
InvokeCustomerRefundDetailsDlg	Method	method InvokeCustomerRefundDetailsDlg	General	Normal
InvokeCustomerSalesDetailsDlg	Method	method InvokeCustomerSalesDetailsDlg	General	Normal
InvokeCustomerTransactionDetailsDlg	Method	method InvokeCustomerTransactionDetailsDlg	General	Normal
InvokeDailyAccountDlg	Method	method InvokeDailyAccountDlg	General	Normal
InvokeDailySummaryDlg	Method	method InvokeDailySummaryDlg	General	Normal
InvokeDiscountSalesDlg	Method	method InvokeDiscountSalesDlg	General	Normal
InvokeMiscTransactionListDlg	Method	method InvokeMiscTransactionListDlg	General	Normal
InvokeMonthlyAccountDlg	Method	method InvokeMonthlyAccountDlg	General	Normal
InvokeMonthlyStatisticsDlg	Method	method InvokeMonthlyStatisticsDlg	General	Normal
InvokeReorderListDlg	Method	method InvokeReorderListDlg	General	Normal
InvokeRollbackDlg	Method	method InvokeRollbackDlg	General	Normal
InvokeSalesListDlg	Method	method InvokeSalesListDlg	General	Normal
InvokeServiceDeliveredDlg	Method	method InvokeServiceDeliveredDlg	General	Normal
InvokeServiceListDlg	Method	method InvokeServiceListDlg	General	Normal
InvokeSpecifiedPeriodAccountDlg	Method	method InvokeSpecifiedPeriodAccountDlg	General	Normal
InvokeStokeListDlg	Method	method InvokeStokeListDlg	General	Normal
InvokeTransactionListDlg	Method	method InvokeTransactionListDlg	General	Normal

ISmpReportMenu overview

ISmpReportMenu::InvokeAnualAccountDlg

method InvokeAnualAccountDlg

```
Sub InvokeAnualAccountDlg
```

No parameters

Method description

It is used to invoke the AnualAccount dialog

Example code

```
CComPtr<ISmpReportMenu>m_SmpReportMenu;  
  
HRESULT hr=m_SmpReportMenu.CoCreateInstance(CLSID_SmpReportMenu);  
  
m_SmpReportMenu->InvokeAnualAccountDlg();
```

[Back to ISmpReportMenu members](#)

ISmpReportMenu::InvokeAnualStatisticsDlg

method InvokeAnualStatisticsDlg

```
Sub InvokeAnualStatisticsDlg
```

No parameters

Method description

It is used to invoke the AnualStatistics dialog

Example code

```
CComPtr<ISmpReportMenu>m_SmpReportMenu;  
  
HRESULT hr=m_SmpReportMenu.CoCreateInstance(CLSID_SmpReportMenu);  
  
m_SmpReportMenu->InvokeAnualStatisticsDlg();
```

[Back to ISmpReportMenu members](#)

ISmpReportMenu::InvokeCanceledSalesDlg

method InvokeCanceledSalesDlg

```
Sub InvokeCanceledSalesDlg
```

No parameters

Method description

It is used to invoke the CanceledSales dialog

Example code

```
CComPtr<ISmpReportMenu>m_SmpReportMenu;  
  
HRESULT hr=m_SmpReportMenu.CoCreateInstance(CLSID_SmpReportMenu);  
  
m_SmpReportMenu->InvokeCanceledSalesDlg();
```

[Back to ISmpReportMenu members](#)

ISmpReportMenu::InvokeCanceledTransactionsDlg

method InvokeCanceledTransactionsDlg

```
Sub InvokeCanceledTransactionsDlg
```

No parameters

Method description

It is used to invoke the CanceledTransactions dialog

Example code

```
CComPtr<ISmpReportMenu>m_SmpReportMenu;  
  
HRESULT hr=m_SmpReportMenu.CoCreateInstance(CLSID_SmpReportMenu);  
  
m_SmpReportMenu->InvokeCanceledTransactionsDlg();
```

[Back to ISmpReportMenu members](#)

ISmpReportMenu::InvokeCustomerBalanceAmountD

method InvokeCustomerBalanceAmountDlg

```
Sub InvokeCustomerBalanceAmountDlg
```

No parameters

Method description

It is used to invoke the CustomerBalanceAmount dialog

Example code

```
CComPtr<ISmpReportMenu>m_SmpReportMenu;  
  
HRESULT hr=m_SmpReportMenu.CoCreateInstance(CLSID_SmpReportMenu);  
  
m_SmpReportMenu->InvokeCustomerBalanceAmountDlg();
```

[Back to ISmpReportMenu members](#)

ISmpReportMenu::InvokeCustomerInactiveDlg

method InvokeCustomerInactiveDlg

```
Sub InvokeCustomerInactiveDlg
```

No parameters

Method description

It is used to invoke the CustomerInactive dialog

Example code

```
CComPtr<ISmpReportMenu>m_SmpReportMenu;  
  
HRESULT hr=m_SmpReportMenu.CoCreateInstance(CLSID_SmpReportMenu);  
  
m_SmpReportMenu->InvokeCustomerInactiveDlg();
```

[Back to ISmpReportMenu members](#)

ISmpReportMenu::InvokeCustomerListDlg

method InvokeCustomerListDlg

```
Sub InvokeCustomerListDlg
```

No parameters

Method description

It is used to invoke the CustomerList dialog

Example code

```
CComPtr<ISmpReportMenu>m_SmpReportMenu;  
  
HRESULT hr=m_SmpReportMenu.CoCreateInstance(CLSID_SmpReportMenu);  
  
m_SmpReportMenu->InvokeCustomerListDlg();
```

[Back to ISmpReportMenu members](#)

ISmpReportMenu::InvokeCustomerMostActiveDlg

method InvokeCustomerMostActiveDlg

```
Sub InvokeCustomerMostActiveDlg
```

No parameters

Method description

It is used to invoke the CustomerMostActive dialog

Example code

```
CComPtr<ISmpReportMenu>m_SmpReportMenu;  
  
HRESULT hr=m_SmpReportMenu.CoCreateInstance(CLSID_SmpReportMenu);  
  
m_SmpReportMenu->InvokeCustomerMostActiveDlg();
```

[Back to ISmpReportMenu members](#)

ISmpReportMenu::InvokeCustomerPaymentDetailsdlg

method InvokeCustomerPaymentDetailsdlg

```
Sub InvokeCustomerPaymentDetailsdlg
```

No parameters

Method description

It is used to invoke the CustomerPaymentDetails dialog

Example code

```
CComPtr<ISmpReportMenu>m_SmpReportMenu;  
  
HRESULT hr=m_SmpReportMenu.CoCreateInstance(CLSID_SmpReportMenu);  
  
m_SmpReportMenu->InvokeCustomerPaymentDetailsdlg();
```

[Back to ISmpReportMenu members](#)

ISmpReportMenu::InvokeCustomerRefundDetailsDlg

method InvokeCustomerRefundDetailsDlg

```
Sub InvokeCustomerRefundDetailsDlg
```

No parameters

Method description

It is used to invoke the CustomerRefundDetails dialog

Example code

```
CComPtr<ISmpReportMenu>m_SmpReportMenu;  
  
HRESULT hr=m_SmpReportMenu.CoCreateInstance(CLSID_SmpReportMenu);  
  
m_SmpReportMenu->InvokeCustomerRefundDetailsDlg();
```

[Back to ISmpReportMenu members](#)

ISmpReportMenu::InvokeCustomerSalesDetailsDlg

method InvokeCustomerSalesDetailsDlg

```
Sub InvokeCustomerSalesDetailsDlg
```

No parameters

Method description

It is used to invoke the CustomerSalesDetails dialog

Example code

```
CComPtr<ISmpReportMenu>m_SmpReportMenu;  
  
HRESULT hr=m_SmpReportMenu.CoCreateInstance(CLSID_SmpReportMenu);  
  
m_SmpReportMenu->InvokeCustomerSalesDetailsDlg();
```

[Back to ISmpReportMenu members](#)

ISmpReportMenu::InvokeCustomerTransactionDetail

method InvokeCustomerTransactionDetailsDlg

```
Sub InvokeCustomerTransactionDetailsDlg
```

No parameters

Method description

It is used to invoke the CustomerTransactionDetails dialog

Example code

```
CComPtr<ISmpReportMenu>m_SmpReportMenu;  
  
HRESULT hr=m_SmpReportMenu.CoCreateInstance(CLSID_SmpReportMenu);  
  
m_SmpReportMenu->InvokeCustomerTransactionDetailsDlg();
```

[Back to ISmpReportMenu members](#)

ISmpReportMenu::InvokeDailyAccountDlg

method InvokeDailyAccountDlg

```
Sub InvokeDailyAccountDlg
```

No parameters

Method description

It is used to invoke the DailyAccount dialog

Example code

```
CComPtr<ISmpReportMenu>m_SmpReportMenu;  
  
HRESULT hr=m_SmpReportMenu.CoCreateInstance(CLSID_SmpReportMenu);  
  
m_SmpReportMenu->InvokeDailyAccountDlg();
```

[Back to ISmpReportMenu members](#)

ISmpReportMenu::InvokeDailySummaryDlg

method InvokeDailySummaryDlg

```
Sub InvokeDailySummaryDlg
```

No parameters

Method description

It is used to invoke the DailySummary dialog

Example code

```
CComPtr<ISmpReportMenu>m_SmpReportMenu;  
  
HRESULT hr=m_SmpReportMenu.CoCreateInstance(CLSID_SmpReportMenu);  
  
m_SmpReportMenu->InvokeDailySummaryDlg();
```

[Back to ISmpReportMenu members](#)

ISmpReportMenu::InvokeDiscountSalesDlg

method InvokeDiscountSalesDlg

```
Sub InvokeDiscountSalesDlg
```

No parameters

Method description

It is used to invoke the DiscountSales dialog

Example code

```
CComPtr<ISmpReportMenu>m_SmpReportMenu;  
  
HRESULT hr=m_SmpReportMenu.CoCreateInstance(CLSID_SmpReportMenu);  
  
m_SmpReportMenu->InvokeDiscountSalesDlg();
```

[Back to ISmpReportMenu members](#)

ISmpReportMenu::InvokeMiscTransactionListDlg

method InvokeMiscTransactionListDlg

```
Sub InvokeMiscTransactionListDlg
```

No parameters

Method description

It is used to invoke the MiscTransactionList dialog

Example code

```
CComPtr<ISmpReportMenu>m_SmpReportMenu;  
  
HRESULT hr=m_SmpReportMenu.CoCreateInstance(CLSID_SmpReportMenu);  
  
m_SmpReportMenu->InvokeMiscTransactionListDlg();
```

[Back to ISmpReportMenu members](#)

ISmpReportMenu::InvokeMonthlyAccountDlg

method InvokeMonthlyAccountDlg

```
Sub InvokeMonthlyAccountDlg
```

No parameters

Method description

It is used to invoke the MonthlyAccount dialog

Example code

```
CComPtr<ISmpReportMenu>m_SmpReportMenu;  
  
HRESULT hr=m_SmpReportMenu.CoCreateInstance(CLSID_SmpReportMenu);  
  
m_SmpReportMenu->InvokeMonthlyAccountDlg();
```

[Back to ISmpReportMenu members](#)

ISmpReportMenu::InvokeMonthlyStatisticsDlg

method InvokeMonthlyStatisticsDlg

```
Sub InvokeMonthlyStatisticsDlg
```

No parameters

Method description

It is used to invoke the MonthlyStatistics dialog

Example code

```
CComPtr<ISmpReportMenu>m_SmpReportMenu;  
  
HRESULT hr=m_SmpReportMenu.CoCreateInstance(CLSID_SmpReportMenu);  
  
m_SmpReportMenu->InvokeMonthlyStatisticsDlg();
```

[Back to ISmpReportMenu members](#)

ISmpReportMenu::InvokeReorderListDlg

method InvokeReorderListDlg

```
Sub InvokeReorderListDlg
```

No parameters

Method description

It is used to invoke the ReorderList dialog

Example code

```
CComPtr<ISmpReportMenu>m_SmpReportMenu;  
  
HRESULT hr=m_SmpReportMenu.CoCreateInstance(CLSID_SmpReportMenu);  
  
m_SmpReportMenu->InvokeReorderListDlg();
```

[Back to ISmpReportMenu members](#)

ISmpReportMenu::InvokeRollbackDlg

method InvokeRollbackDlg

```
Sub InvokeRollbackDlg
```

No parameters

Method description

It is used to invoke the Rollback dialog

Example code

```
CComPtr<ISmpReportMenu>m_SmpReportMenu;  
  
HRESULT hr=m_SmpReportMenu.CoCreateInstance(CLSID_SmpReportMenu);  
  
m_SmpReportMenu->InvokeRollbackDlg();
```

[Back to ISmpReportMenu members](#)

ISmpReportMenu::InvokeSalesListDlg

method InvokeSalesListDlg

```
Sub InvokeSalesListDlg
```

No parameters

Method description

It is used to invoke the SalesList dialog

Example code

```
CComPtr<ISmpReportMenu>m_SmpReportMenu;  
  
HRESULT hr=m_SmpReportMenu.CoCreateInstance(CLSID_SmpReportMenu);  
  
m_SmpReportMenu->InvokeSalesListDlg();
```

[Back to ISmpReportMenu members](#)

ISmpReportMenu::InvokeServiceDeliveredDlg

method InvokeServiceDeliveredDlg

```
Sub InvokeServiceDeliveredDlg
```

No parameters

Method description

It is used to invoke the ServiceDelivered dialog

Example code

```
CComPtr<ISmpReportMenu>m_SmpReportMenu;  
  
HRESULT hr=m_SmpReportMenu.CoCreateInstance(CLSID_SmpReportMenu);  
  
m_SmpReportMenu->InvokeServiceDeliveredDlg();
```

[Back to ISmpReportMenu members](#)

ISmpReportMenu::InvokeServiceListDlg

method InvokeServiceListDlg

```
Sub InvokeServiceListDlg
```

No parameters

Method description

It is used to invoke the ServiceList dialog

Example code

```
CComPtr<ISmpReportMenu>m_SmpReportMenu;  
  
HRESULT hr=m_SmpReportMenu.CoCreateInstance(CLSID_SmpReportMenu);  
  
m_SmpReportMenu->InvokeServiceListDlg();
```

[Back to ISmpReportMenu members](#)

ISmpReportMenu::InvokeSpecifiedPeriodAccountDlg

method InvokeSpecifiedPeriodAccountDlg

```
Sub InvokeSpecifiedPeriodAccountDlg
```

No parameters

Method description

It is used to invoke the SpecifiedPeriodAccount dialog

Example code

```
CComPtr<ISmpReportMenu>m_SmpReportMenu;  
  
HRESULT hr=m_SmpReportMenu.CoCreateInstance(CLSID_SmpReportMenu);  
  
m_SmpReportMenu->InvokeSpecifiedPeriodAccountDlg();
```

[Back to ISmpReportMenu members](#)

ISmpReportMenu::InvokeStokeListDlg

method InvokeStokeListDlg

```
Sub InvokeStokeListDlg
```

No parameters

Method description

It is used to invoke the StokeList dialog

Example code

```
CComPtr<ISmpReportMenu>m_SmpReportMenu;  
  
HRESULT hr=m_SmpReportMenu.CoCreateInstance(CLSID_SmpReportMenu);  
  
m_SmpReportMenu->InvokeStokeListDlg();
```

[Back to ISmpReportMenu members](#)

ISmpReportMenu::InvokeTransactionListDlg

method InvokeTransactionListDlg

```
Sub InvokeTransactionListDlg
```

No parameters

Method description

It is used to invoke the TransactionList dialog

Example code

```
CComPtr<ISmpReportMenu>m_SmpReportMenu;  
  
HRESULT hr=m_SmpReportMenu.CoCreateInstance(CLSID_SmpReportMenu);  
  
m_SmpReportMenu->InvokeTransactionListDlg();
```

[Back to ISmpReportMenu members](#)

Coclass: ISmpReportMenuEvents

Interface: IIISmpReportMenuEvents

[Browse members alphabetically](#)

[Browse members by category](#)

[Browse members by use](#)

IISmpReportMenuEvents members

Properties

Name	Type	HelpString	Category	Frequency of use
OnAnualStatisticsReport	Method	method OnAnualStatisticsReport	General	Normal
OnMonthlyStatisticsReport	Method	method OnMonthlyStatisticsReport	General	Normal

[IISmpReportMenuEvents](#) overview

IISmpReportMenuEvents::OnAnualStatisticsReport

method OnAnualStatisticsReport

```
Sub OnAnualStatisticsReport(strYear As String, varGenericReport)
```

Parameters

No	Name	Type	Optional	Default	Description
1	strYear	String	No	-	
2	varGenericReport	Variant	No	-	

Method description

This Method is used to display the Annual report.

[Back to IISmpReportMenuEvents members](#)

IISmpReportMenuEvents::OnMonthlyStatisticsReport

method OnMonthlyStatisticsReport

```
Sub OnMonthlyStatisticsReport(strMonth As String, strYear As  
String, varGenericReport)
```

Parameters

No	Name	Type	Optional	Default	Description
1	strMonth	String	No	-	
2	strYear	String	No	-	
3	varGenericReport	Variant	No	-	

Method description

This Method is used to display the Monthly report.

[Back to IISmpReportMenuEvents members](#)

ICustomer members by category

Properties

Name	Type	HelpString	Category	Frequency of use
GetCustomerDetails	Method	method GetCustomerDetails	General	Normal
InvokeFindCustomerDlg	Method	method InvokeFindCustomerDlg	General	Normal

[ICustomer overview](#)

ICustomer members by frequency of use

Properties

Name	Type	HelpString	Category	Frequency of use
GetCustomerDetails	Method	method GetCustomerDetails	General	Normal
InvokeFindCustomerDlg	Method	method InvokeFindCustomerDlg	General	Normal

[ICustomer overview](#)

IIItem members by category

Properties

Name	Type	HelpString	Category	Frequency of use
Col	Property Get/Let	property Col	General	Normal
Content	Property Get/Let	property Content	General	Normal
ContentType	Property Get/Let	property ContentType	General	Normal
HAlign	Property Get/Let	property HAlign	General	Normal
MaxCol	Property Get/Let	property MaxCol	General	Normal
MaxRow	Property Get/Let	property MaxRow	General	Normal
Row	Property Get/Let	property Row	General	Normal

Item overview

IIItem members by frequency of use

Properties

Name	Type	HelpString	Category	Frequency of use
Col	Property Get/Let	property Col	General	Normal
Content	Property Get/Let	property Content	General	Normal
ContentType	Property Get/Let	property ContentType	General	Normal
HAlign	Property Get/Let	property HAlign	General	Normal
MaxCol	Property Get/Let	property MaxCol	General	Normal
MaxRow	Property Get/Let	property MaxRow	General	Normal
Row	Property Get/Let	property Row	General	Normal

Item overview

IReports members by category

Properties

Name	Type	HelpString	Category	Frequency of use
FillReport	Method	method FillReport	General	Normal
FillReportEx	Method	method FillReportEx	General	Normal
FillReportWithCaption	Method	method FillReportWithCaption	General	Normal

[IReports overview](#)

IReports members by frequency of use

Properties

Name	Type	HelpString	Category	Frequency of use
FillReportEx	Method	method FillReportEx	General	Normal
FillReportWithCaption	Method	method FillReportWithCaption	General	Normal
FillReport	Method	method FillReport	General	Normal

[IReports overview](#)

ITansactionEvents members by category

Properties

Name	Type	HelpString	Category	Frequency of use
OnAddTransaction	Method	method OnAddTransaction	General	Normal
OnDeleteTransaction	Method	method OnDeleteTransaction	General	Normal
OnEditTransaction	Method	method OnEditTransaction	General	Normal

[ITransactionEvents overview](#)

ITransactionEvents members by frequency of use

Properties

Name	Type	HelpString	Category	Frequency of use
OnAddTransaction	Method	method OnAddTransaction	General	Normal
OnDeleteTransaction	Method	method OnDeleteTransaction	General	Normal
OnEditTransaction	Method	method OnEditTransaction	General	Normal

[ITransactionEvents overview](#)

ISalesCheckout members by category

Properties

Name	Type	HelpString	Category	Frequency of use
InvokeSalesCheckoutDlg	Method	method InvokeSalesCheckoutDlg	General	Normal

[ISalesCheckout overview](#)

ISalesCheckout members by frequency of use

Properties

Name	Type	HelpString	Category	Frequency of use
InvokeSalesCheckoutDlg	Method	method InvokeSalesCheckoutDlg	General	Normal

[ISalesCheckout overview](#)

ISalesCheckoutEvents members by category

Properties

Name	Type	HelpString	Category	Frequency of use
OnCheckout	Method	method OnCheckout	General	Normal

[ISalesCheckoutEvents overview](#)

ISalesCheckoutEvents members by frequency of use

Properties

Name	Type	HelpString	Category	Frequency of use
OnCheckout	Method	method OnCheckout	General	Normal

[ISalesCheckoutEvents overview](#)

ITransactions members by category

Properties

Name	Type	HelpString	Category	Frequency of use
InvokeAddMiscExpenseDlg	Method	method InvokeAddMiscExpenseDlg	General	Normal
InvokeAddMiscIncomeDlg	Method	method InvokeAddMiscIncomeDlg	General	Normal
InvokeAddTransactionDlg	Method	method InvokeAddTransactionDlg	General	Normal
InvokeCancelTransactionDlg	Method	method InvokeCancelTransactionDlg	General	Normal
InvokeEditMiscExpenseDlg	Method	method InvokeEditMiscExpenseDlg	General	Normal
InvokeEditMiscIncomeDlg	Method	method InvokeEditMiscIncomeDlg	General	Normal
InvokeEditTransactionDlg	Method	method InvokeEditTransactionDlg	General	Normal

ITransactions overview

ITransactions members by frequency of use

Properties

Name	Type	HelpString	Category	Frequency of use
InvokeAddMiscExpenseDlg	Method	method InvokeAddMiscExpenseDlg	General	Normal
InvokeAddMiscIncomeDlg	Method	method InvokeAddMiscIncomeDlg	General	Normal
InvokeAddTransactionDlg	Method	method InvokeAddTransactionDlg	General	Normal
InvokeCancelTransactionDlg	Method	method InvokeCancelTransactionDlg	General	Normal
InvokeEditMiscExpenseDlg	Method	method InvokeEditMiscExpenseDlg	General	Normal
InvokeEditMiscIncomeDlg	Method	method InvokeEditMiscIncomeDlg	General	Normal
InvokeEditTransactionDlg	Method	method InvokeEditTransactionDlg	General	Normal

ITransactions overview

ISettings members by category

Properties

Name	Type	HelpString	Category	Frequency of use
AutomaticBackup	Property Get	property AutomaticBackup	General	Normal
AutomaticCompact	Property Get	property AutomaticCompact	General	Normal
CompactDatabase	Method	method CompactDatabase	General	Normal
DateFormat	Property Get	property DateFormat	General	Normal
DefaultMembershipFee	Property Get	property DefaultMembershipFee	General	Normal
DefaultSecurityDeposit	Property Get	property DefaultSecurityDeposit	General	Normal
LaunchOnStartup	Property Get	property LaunchOnStartup	General	Normal
NoOfDisplayRecords	Property Get	property NoOfDisplayRecords	General	Normal
OverrideExDataOnAB	Property Get	property OverrideExDataOnAB	General	Normal
PaymentMethod	Property Get/Let	property PaymentMethod	General	Normal
PictureFolder	Property Get	property PictureFolder	General	Normal
UseEnterKey	Property Get	property UseEnterKey	General	Normal

[ISettings overview](#)

ISettings members by frequency of use

Properties

Name	Type	HelpString	Category	Frequency of use
AutomaticBackup	Property Get	property AutomaticBackup	General	Normal
AutomaticCompact	Property Get	property AutomaticCompact	General	Normal
CompactDatabase	Method	method CompactDatabase	General	Normal
DateFormat	Property Get	property DateFormat	General	Normal
DefaultMembershipFee	Property Get	property DefaultMembershipFee	General	Normal
DefaultSecurityDeposit	Property Get	property DefaultSecurityDeposit	General	Normal
LaunchOnStartup	Property Get	property LaunchOnStartup	General	Normal
NoOfDisplayRecords	Property Get	property NoOfDisplayRecords	General	Normal
OverrideExDataOnAB	Property Get	property OverrideExDataOnAB	General	Normal
PaymentMethod	Property Get/Let	property PaymentMethod	General	Normal
PictureFolder	Property Get	property PictureFolder	General	Normal
UseEnterKey	Property Get	property UseEnterKey	General	Normal

[ISettings overview](#)

ISecurity members by category

Properties

Name	Type	HelpString	Category	Frequency of use
AccessCustomerMenu	Property Get	property AccessCustomerMenu	General	Normal
AccessSalesMenu	Property Get	property AccessSalesMenu	General	Normal
AccessSetup	Property Get	property AccessSetup	General	Normal
AccessTransactionMenu	Property Get	property AccessTransactionMenu	General	Normal
CurrentLoginUser	Property Get	property CurrentLoginUser	General	Normal
CurrentUserRights	Property Get	property CurrentUserRights	General	Normal
DatabaseRight	Property Get	property DatabaseRight	General	Normal
 GetUserRightsInfo	Method	method GetUserRightsInfo	General	Normal
PrintReports	Property Get	property PrintReports	General	Normal
UpdateShopBalance	Property Get	property UpdateShopBalance	General	Normal
UserRightInfo	Property Get	property UserRightInfo	General	Normal
ViewReports	Property Get	property ViewReports	General	Normal

[ISecurity overview](#)

ISecurity members by frequency of use

Properties

Name	Type	HelpString	Category	Frequency of use
AccessCustomerMenu	Property Get	property AccessCustomerMenu	General	Normal
AccessSalesMenu	Property Get	property AccessSalesMenu	General	Normal
AccessSetup	Property Get	property AccessSetup	General	Normal
AccessTransactionMenu	Property Get	property AccessTransactionMenu	General	Normal
CurrentLoginUser	Property Get	property CurrentLoginUser	General	Normal
CurrentUserRights	Property Get	property CurrentUserRights	General	Normal
DatabaseRight	Property Get	property DatabaseRight	General	Normal
 GetUserRightsInfo	Method	method GetUserRightsInfo	General	Normal
PrintReports	Property Get	property PrintReports	General	Normal
UpdateShopBalance	Property Get	property UpdateShopBalance	General	Normal
UserRightInfo	Property Get	property UserRightInfo	General	Normal
ViewReports	Property Get	property ViewReports	General	Normal

[ISecurity overview](#)

IDatabase members by category

Properties

Name	Type	HelpString	Category	Frequency of use
ConnectionInterface	Property Get	property ConnectionInterface	General	Normal
DBPath	Property Get	property DBPath	General	Normal
ExecuteQuery	Method	method ExecuteQuery	General	Normal
ExecuteQueryEx	Method	method ExecuteQueryEx	General	Normal
IsMSAccess	Property Get	property IsMSAccess	General	Normal

[IDatabase overview](#)

IDatabase members by frequency of use

Properties

Name	Type	HelpString	Category	Frequency of use
ConnectionInterface	Property Get	property ConnectionInterface	General	Normal
DBPath	Property Get	property DBPath	General	Normal
ExecuteQuery	Method	method ExecuteQuery	General	Normal
ExecuteQueryEx	Method	method ExecuteQueryEx	General	Normal
IsMSAccess	Property Get	property IsMSAccess	General	Normal

[IDatabase overview](#)

IGrid members by category

Properties

Name	Type	HelpString	Category	Frequency of use
CellColour	Property Get/Let	property CellColour	General	Normal
CellFont	Property Get/Let	property CellFont	General	Normal
CellFontSize	Property Get/Let	property CellFontSize	General	Normal
CellFontType	Property Get/Let	property CellFontType	General	Normal
CellText	Property Get/Let	property CellText	General	Normal
CellTextColour	Property Get/Let	property CellTextColour	General	Normal
ColumnWidth	Property Get/Let	property ColumnWidth	General	Normal
DeleteColumn	Method	method DeleteColumn	General	Normal
DeleteRow	Method	method DeleteRow	General	Normal
HorizontalGridLine	Property Get/Let	property HorizontalGridLine	General	Normal
InsertColumn	Method	method InsertColumn	General	Normal
InsertRow	Method	method InsertRow	General	Normal
MergeCells	Method	method MergeCells	General	Normal
NoOfColumns	Property Get/Let	property NoOfColumns	General	Normal
NoOfFixedColumns	Property Get/Let	property NoOfFixedColumns	General	Normal
NoOfFixedRows	Property Get/Let	property NoOfFixedRows	General	Normal
NoOfRows	Property Get/Let	property NoOfRows	General	Normal
PrintContents	Method	method PrintContents	General	Normal
ReadOnly	Property Get/Let	property ReadOnly	General	Normal
ResetGrid	Method	method ResetGrid	General	Normal
RowHeight	Property Get/Let	property RowHeight	General	Normal
UnmergeCells	Method	method UnmergeCells	General	Normal
VerticalGridLine	Property Get/Let	property VerticalGridLine	General	Normal
WindowHandle	Property Get	property WindowHandle	General	Normal

[IGrid overview](#)

IGrid members by frequency of use

Properties

Name	Type	HelpString	Category	Frequency of use
CellColour	Property Get/Let	property CellColour	General	Normal
CellFont	Property Get/Let	property CellFont	General	Normal
CellFontSize	Property Get/Let	property CellFontSize	General	Normal
CellFontType	Property Get/Let	property CellFontType	General	Normal
CellText	Property Get/Let	property CellText	General	Normal
CellTextColour	Property Get/Let	property CellTextColour	General	Normal
ColumnWidth	Property Get/Let	property ColumnWidth	General	Normal
DeleteColumn	Method	method DeleteColumn	General	Normal
DeleteRow	Method	method DeleteRow	General	Normal
HorizontalGridLine	Property Get/Let	property HorizontalGridLine	General	Normal
InsertColumn	Method	method InsertColumn	General	Normal
InsertRow	Method	method InsertRow	General	Normal
MergeCells	Method	method MergeCells	General	Normal
NoOfColumns	Property Get/Let	property NoOfColumns	General	Normal
NoOfFixedColumns	Property Get/Let	property NoOfFixedColumns	General	Normal
NoOfFixedRows	Property Get/Let	property NoOfFixedRows	General	Normal
NoOfRows	Property Get/Let	property NoOfRows	General	Normal
PrintContents	Method	method PrintContents	General	Normal
ReadOnly	Property Get/Let	property ReadOnly	General	Normal
ResetGrid	Method	method ResetGrid	General	Normal
RowHeight	Property Get/Let	property RowHeight	General	Normal
UnmergeCells	Method	method UnmergeCells	General	Normal
VerticalGridLine	Property Get/Let	property VerticalGridLine	General	Normal
WindowHandle	Property Get	property WindowHandle	General	Normal

[IGrid overview](#)

Interface: ISmpSettingsEx

[Browse members alphabetically](#)

[Browse members by category](#)

[Browse members by use](#)

ISmpOEMEvents members by category

Properties

Name	Type	HelpString	Category	Frequency of use
InvokeCustomAccountsMenuDlg	Method	method InvokeCustomAccountsMenuDlg	General	Normal
InvokeCustomCustomerMenuDlg	Method	method InvokeCustomCustomerMenuDlg	General	Normal
InvokeCustomFileMenuDlg	Method	method InvokeCustomFileMenuDlg	General	Normal
InvokeCustomHelpMenuDlg	Method	method InvokeCustomHelpMenuDlg	General	Normal
InvokeCustomReportMenuDlg	Method	method InvokeCustomReportMenuDlg	General	Normal
InvokeCustomSalesMenuDlg	Method	method InvokeCustomSalesMenuDlg	General	Normal
InvokeCustomSetupMenuDlg	Method	method InvokeCustomSetupMenuDlg	General	Normal
InvokeCustomTransactionMenuDlg	Method	method InvokeCustomTransactionMenuDlg	General	Normal
InvokeCustomViewMenu	Method	method InvokeCustomViewMenu	General	Normal

[ISmpOEMEvents overview](#)

ISmpOEMEvents members by frequency of use

Properties

Name	Type	HelpString	Category	Frequency of use
InvokeCustomAccountsMenuDlg	Method	method InvokeCustomAccountsMenuDlg	General	Normal
InvokeCustomCustomerMenuDlg	Method	method InvokeCustomCustomerMenuDlg	General	Normal
InvokeCustomFileMenuDlg	Method	method InvokeCustomFileMenuDlg	General	Normal
InvokeCustomHelpMenuDlg	Method	method InvokeCustomHelpMenuDlg	General	Normal
InvokeCustomReportMenuDlg	Method	method InvokeCustomReportMenuDlg	General	Normal
InvokeCustomSalesMenuDlg	Method	method InvokeCustomSalesMenuDlg	General	Normal
InvokeCustomSetupMenuDlg	Method	method InvokeCustomSetupMenuDlg	General	Normal
InvokeCustomTransactionMenuDlg	Method	method InvokeCustomTransactionMenuDlg	General	Normal
InvokeCustomViewMenu	Method	method InvokeCustomViewMenu	General	Normal

[ISmpOEMEvents overview](#)

ISmpGrid members by category

Properties

Name	Type	HelpString	Category	Frequency of use
AutoSize	Method	method AutoSize	General	Normal
ColumnResize	Property Get/Let	property ColumnResize	General	Normal
GridObj	Property Get	property GridObj	General	Normal
IsCellMerged	Property Get	property IsCellMerged	General	Normal
RowResize	Property Get/Let	property RowResize	General	Normal
SelectedCellCount	Property Get	property SelectedCellCount	General	Normal
SetAutoSizeStyle	Method	method SetAutoSizeStyle	General	Normal
SetFocusCell	Method	method SetFocusCell	General	Normal

[ISmpGrid overview](#)

ISmpGrid members by frequency of use

Properties

Name	Type	HelpString	Category	Frequency of use
AutoSize	Method	method AutoSize	General	Normal
ColumnResize	Property Get/Let	property ColumnResize	General	Normal
GridObj	Property Get	property GridObj	General	Normal
IsCellMerged	Property Get	property IsCellMerged	General	Normal
RowResize	Property Get/Let	property RowResize	General	Normal
SelectedCellCount	Property Get	property SelectedCellCount	General	Normal
SetAutoSizeStyle	Method	method SetAutoSizeStyle	General	Normal
SetFocusCell	Method	method SetFocusCell	General	Normal

[ISmpGrid overview](#)

ISmpGridCtrl members by category

Properties

Name	Type	HelpString	Category	Frequency of use
AutoSize	Method	method AutoSize	General	Normal
DeleteAllImages	Method	method DeleteAllImages	General	Normal
DeleteAllItems	Method	method DeleteAllItems	General	Normal
GridBkgColor	Property Get/Let	property GridBkgColor	General	Normal
GridCtrlObj	Property Get	property GridCtrlObj	General	Normal
RefreshCtrl	Method	method RefreshCtrl	General	Normal
SetBusinessLogo	Method	method SetBusinessLogo	General	Normal
SetCellImage	Method	method SetCellImage	General	Normal
SetCellImageEx	Method	method SetCellImageEx	General	Normal
SetCellText	Method	method SetCellText	General	Normal
SetCellTextAlignment	Method	method SetCellTextAlignment	General	Normal
SetCellTextWrap	Method	method SetCellTextWrap	General	Normal
SetDefaultColumnWidth	Method	method SetDefaultColumnWidth	General	Normal
SetDefaultRowHeight	Method	method SetDefaultRowHeight	General	Normal
SetGridDisplayReadOnly	Method	method SetGridDisplayReadOnly	General	Normal
SetWordWrapMode	Method	method SetWordWrapMode	General	Normal

[ISmpGridCtrl overview](#)

ISmpGridCtrl members by frequency of use

Properties

Name	Type	HelpString	Category	Frequency of use
AutoSize	Method	method AutoSize	General	Normal
DeleteAllImages	Method	method DeleteAllImages	General	Normal
DeleteAllItems	Method	method DeleteAllItems	General	Normal
GridBkgColor	Property Get/Let	property GridBkgColor	General	Normal
GridCtrlObj	Property Get	property GridCtrlObj	General	Normal
RefreshCtrl	Method	method RefreshCtrl	General	Normal
SetBusinessLogo	Method	method SetBusinessLogo	General	Normal
SetCellImage	Method	method SetCellImage	General	Normal
SetCellImageEx	Method	method SetCellImageEx	General	Normal
SetCellText	Method	method SetCellText	General	Normal
SetCellTextAlignment	Method	method SetCellTextAlignment	General	Normal
SetCellTextWrap	Method	method SetCellTextWrap	General	Normal
SetDefaultColumnWidth	Method	method SetDefaultColumnWidth	General	Normal
SetDefaultRowHeight	Method	method SetDefaultRowHeight	General	Normal
SetGridDisplayReadOnly	Method	method SetGridDisplayReadOnly	General	Normal
SetWordWrapMode	Method	method SetWordWrapMode	General	Normal

[ISmpGridCtrl overview](#)

ISmpApp members by category

Properties

Name	Type	HelpString	Category	Frequency of use
IsRegistered	Property Get	property IsRegistered	General	Normal
SendStatus	Method	method SendStatus	General	Normal
SetAddInInfo	Method	method SetAddInInfo	General	Normal
SetAddinSecurityInfo	Method	method SetAddinSecurityInfo	General	Normal
WindowHandle	Property Get	property WindowHandle	General	Normal

[ISmpApp overview](#)

ISmpApp members by frequency of use

Properties

Name	Type	HelpString	Category	Frequency of use
WindowHandle	Property Get	property WindowHandle	General	Normal
IsRegistered	Property Get	property IsRegistered	General	Normal
SendStatus	Method	method SendStatus	General	Normal
SetAddInInfo	Method	method SetAddInInfo	General	Normal
SetAddinSecurityInfo	Method	method SetAddinSecurityInfo	General	Normal

[ISmpApp overview](#)

ISmpAddin members by category

Properties

Name	Type	HelpString	Category	Frequency of use
ApplicationLaunched	Method	method ApplicationLaunched	General	Normal
CheckCredentials	Method	method CheckCredentials	General	Normal
DeleteOldData	Method	method DeleteOldData	General	Normal
Initialize	Method	method Initialize	General	Normal
InitializeDatabase	Method	method InitializeDatabase	General	Normal
InvokeAboutBox	Method	method InvokeAboutBox	General	Normal
Uninitialize	Method	method Uninitialize	General	Normal
UpdateAddinCmdUI	Method	method UpdateAddinCmdUI	General	Normal

[ISmpAddin](#) overview

ISmpAddin members by frequency of use

Properties

Name	Type	HelpString	Category	Frequency of use
CheckCredentials	Method	method CheckCredentials	General	Normal
DeleteOldData	Method	method DeleteOldData	General	Normal
Initialize	Method	method Initialize	General	Normal
InitializeDatabase	Method	method InitializeDatabase	General	Normal
InvokeAboutBox	Method	method InvokeAboutBox	General	Normal
Uninitialize	Method	method Uninitialize	General	Normal
UpdateAddinCmdUI	Method	method UpdateAddinCmdUI	General	Normal
ApplicationLaunched	Method	method ApplicationLaunched	General	Normal

[**ISmpAddin overview**](#)

IAccounts members by category

Properties

Name	Type	HelpString	Category	Frequency of use
AddToShopBalance	Method	method AddToShopBalance	General	Normal
InvokeAcceptPaymentDialog	Method	method InvokeAcceptPaymentDialog	General	Normal
InvokeRefundToCustomerDlg	Method	method InvokeRefundToCustomerDlg	General	Normal
SubstractFromShopBalance	Method	method SubstractFromShopBalance	General	Normal

[IAccounts overview](#)

I Accounts members by frequency of use

Properties

Name	Type	HelpString	Category	Frequency of use
InvokeAcceptPaymentDialog	Method	method InvokeAcceptPaymentDialog	General	Normal
InvokeRefundToCustomerDlg	Method	method InvokeRefundToCustomerDlg	General	Normal
SubstractFromShopBalance	Method	method SubstractFromShopBalance	General	Normal
AddToShopBalance	Method	method AddToShopBalance	General	Normal

[IAccounts overview](#)

IAccountsEvents members by category

Properties

Name	Type	HelpString	Category	Frequency of use
AddAdvancedReportPage	Method	method AddAdvancedReportPage	General	Normal
OnAccountReport	Method	method OnAccountReport	General	Normal
OnTransactionAccountDetails	Method	method OnTransactionAccountDetails	General	Normal

[IAccountsEvents overview](#)

IAccountsEvents members by frequency of use

Properties

Name	Type	HelpString	Category	Frequency of use
AddAdvancedReportPage	Method	method AddAdvancedReportPage	General	Normal
OnAccountReport	Method	method OnAccountReport	General	Normal
OnTransactionAccountDetails	Method	method OnTransactionAccountDetails	General	Normal

[IAccountsEvents overview](#)

ISmpDialogEvents members by category

Properties

Name	Type	HelpString	Category	Frequency of use
OnDialogWndProc	Method	method OnDialogWndProc	General	Normal

[ISmpDialogEvents overview](#)

ISmpDialogEvents members by frequency of use

Properties

Name	Type	HelpString	Category	Frequency of use
OnDialogWndProc	Method	method OnDialogWndProc	General	Normal

[ISmpDialogEvents overview](#)

ISmpReport members by category

Properties

Name	Type	HelpString	Category	Frequency of use
FillReport	Method	method FillReport	General	Normal
GetBodyFormat	Method	method GetBodyFormat	General	Normal
GetFooterFormat	Method	method GetFooterFormat	General	Normal
GetFooterInfo	Method	method GetFooterInfo	General	Normal
GetHeaderFormat	Method	method GetHeaderFormat	General	Normal
GetHeaderInfo	Method	method GetHeaderInfo	General	Normal
PrintReport	Method	method PrintReport	General	Normal
ResetContent	Method	method ResetContent	General	Normal
SetBodyFormat	Method	method SetBodyFormat	General	Normal
SetFooterFormat	Method	method SetFooterFormat	General	Normal
SetFooterInfo	Method	method SetFooterInfo	General	Normal
SetHeaderFormat	Method	method SetHeaderFormat	General	Normal
SetHeaderInfo	Method	method SetHeaderInfo	General	Normal

[ISmpReport](#) overview

ISmpReport members by frequency of use

Properties

Name	Type	HelpString	Category	Frequency of use
FillReport	Method	method FillReport	General	Normal
GetBodyFormat	Method	method GetBodyFormat	General	Normal
GetFooterFormat	Method	method GetFooterFormat	General	Normal
GetFooterInfo	Method	method GetFooterInfo	General	Normal
GetHeaderFormat	Method	method GetHeaderFormat	General	Normal
GetHeaderInfo	Method	method GetHeaderInfo	General	Normal
PrintReport	Method	method PrintReport	General	Normal
ResetContent	Method	method ResetContent	General	Normal
SetBodyFormat	Method	method SetBodyFormat	General	Normal
SetFooterFormat	Method	method SetFooterFormat	General	Normal
SetFooterInfo	Method	method SetFooterInfo	General	Normal
SetHeaderFormat	Method	method SetHeaderFormat	General	Normal
SetHeaderInfo	Method	method SetHeaderInfo	General	Normal

[ISmpReport](#) overview

IISmpCommands members by category

Properties

<i>Name</i>	<i>Type</i>	<i>HelpString</i>	<i>Category</i>	<i>Frequency of use</i>
MenuCommandEx	Property Get	property MenuCommandEx	General	Normal
MenuCommandID	Property Get	property MenuCommandID	General	Normal
MenuString	Property Get	property MenuString	General	Normal
NoOfCommands	Property Get	property NoOfCommands	General	Normal

[IIISmpCommands overview](#)

IISmpCommands members by frequency of use

Properties

Name	Type	HelpString	Category	Frequency of use
MenuCommandEx	Property Get	property MenuCommandEx	General	Normal
MenuCommandID	Property Get	property MenuCommandID	General	Normal
MenuString	Property Get	property MenuString	General	Normal
NoOfCommands	Property Get	property NoOfCommands	General	Normal

[IISmpCommands overview](#)

IISmpGenericReport members by category

Properties

Name	Type	HelpString	Category	Frequency of use
AddBodyContents	Method	method AddBodyContents	General	Normal
AddBodyContentsEx	Method	method AddBodyContentsEx	General	Normal
AddFooterContents	Method	method AddFooterContents	General	Normal
AddFooterContentsEx	Method	method AddFooterContentsEx	General	Normal
AddMergeInfo	Method	method AddMergeInfo	General	Normal
AddReportHeading	Method	method AddReportHeading	General	Normal
AddReportHeadingEx	Method	method AddReportHeadingEx	General	Normal
BodyCellArrayCount	Property Get	property BodyCellArrayCount	General	Normal
BodyItem	Property Get	property BodyItem	General	Normal
BodyProperties	Property Get/Let	property BodyProperties	General	Normal
FillReport	Method	method FillReport	General	Normal
FooterCellArrayCount	Property Get	property FooterCellArrayCount	General	Normal
FooterItem	Property Get	property FooterItem	General	Normal
FooterProperties	Property Get/Let	property FooterProperties	General	Normal
GenericReportObj	Property Get	property GenericReportObj	General	Normal
GenericReportProperties	Property Get/Let	property GenericReportProperties	General	Normal
HeaderCellArrayCount	Property Get	property HeaderCellArrayCount	General	Normal
HeaderItem	Property Get	property HeaderItem	General	Normal
HeaderProperties	Property Get/Let	property HeaderProperties	General	Normal
HeadingItalic	Property Get/Let	property HeadingItalic	General	Normal
ItemCount	Property Get/Let	property ItemCount	General	Normal
MergeCellProperties	Property Get/Let	property MergeCellProperties	General	Normal
RemoveAllContents	Method	method RemoveAllContents	General	Normal
RemoveBodyContents	Method	method RemoveBodyContents	General	Normal
RemoveFooterContents	Method	method RemoveFooterContents	General	Normal
RemoveHeaderContents	Method	method RemoveHeaderContents	General	Normal
RemoveLastFooterContent	Method	method RemoveLastFooterContent	General	Normal

ReportType	Property Get/Let	property ReportType	General	Normal
SetBodySize	Method	method SetBodySize	General	Normal
SetFooterSize	Method	method SetFooterSize	General	Normal
SetGenericReportObj	Method	method SetGenericReportObj	General	Normal
SetHeaderMargin	Method	method SetHeaderMargin	General	Normal
SetHeaderSize	Method	method SetHeaderSize	General	Normal

IISmpGenericReport overview

IISmpGenericReport members by frequency of use

Properties

Name	Type	HelpString	Category	Frequency of use
AddBodyContents	Method	method AddBodyContents	General	Normal
AddBodyContentsEx	Method	method AddBodyContentsEx	General	Normal
AddFooterContents	Method	method AddFooterContents	General	Normal
AddFooterContentsEx	Method	method AddFooterContentsEx	General	Normal
AddMergeInfo	Method	method AddMergeInfo	General	Normal
AddReportHeading	Method	method AddReportHeading	General	Normal
AddReportHeadingEx	Method	method AddReportHeadingEx	General	Normal
BodyCellArrayCount	Property Get	property BodyCellArrayCount	General	Normal
BodyItem	Property Get	property BodyItem	General	Normal
BodyProperties	Property Get/Let	property BodyProperties	General	Normal
FillReport	Method	method FillReport	General	Normal
FooterCellArrayCount	Property Get	property FooterCellArrayCount	General	Normal
FooterItem	Property Get	property FooterItem	General	Normal
FooterProperties	Property Get/Let	property FooterProperties	General	Normal
GenericReportObj	Property Get	property GenericReportObj	General	Normal
GenericReportProperties	Property Get/Let	property GenericReportProperties	General	Normal
HeaderCellArrayCount	Property Get	property HeaderCellArrayCount	General	Normal
HeaderItem	Property Get	property HeaderItem	General	Normal
HeaderProperties	Property Get/Let	property HeaderProperties	General	Normal
HeadingItalic	Property Get/Let	property HeadingItalic	General	Normal
ItemCount	Property Get/Let	property ItemCount	General	Normal
MergeCellProperties	Property Get/Let	property MergeCellProperties	General	Normal
RemoveAllContents	Method	method RemoveAllContents	General	Normal
RemoveBodyContents	Method	method RemoveBodyContents	General	Normal
RemoveFooterContents	Method	method RemoveFooterContents	General	Normal
RemoveHeaderContents	Method	method RemoveHeaderContents	General	Normal
RemoveLastFooterContent	Method	method RemoveLastFooterContent	General	Normal

ReportType	Property Get/Let	property ReportType	General	Normal
SetBodySize	Method	method SetBodySize	General	Normal
SetFooterSize	Method	method SetFooterSize	General	Normal
SetGenericReportObj	Method	method SetGenericReportObj	General	Normal
SetHeaderMargin	Method	method SetHeaderMargin	General	Normal
SetHeaderSize	Method	method SetHeaderSize	General	Normal

IISmpGenericReport overview

ISmpView members by category

Properties

Name	Type	HelpString	Category	Frequency of use
PrintInDosMode	Method	method PrintInDosMode	General	Normal
PrintReport	Method	method PrintReport	General	Normal

[ISmpView overview](#)

ISmpView members by frequency of use

Properties

Name	Type	HelpString	Category	Frequency of use
PrintInDosMode	Method	method PrintInDosMode	General	Normal
PrintReport	Method	method PrintReport	General	Normal

[ISmpView overview](#)

ISmpPluginTab members by category

Properties

Name	Type	HelpString	Category	Frequency of use
AddSmpPage	Method	method AddSmpPage	General	Normal
AddView	Method	method AddView	General	Normal
CreateFormView	Method	method CreateFormView	General	Normal
CreateView	Method	method CreateView	General	Normal
CreateWinFormsView	Method	method CreateWinFormsView	General	Normal
GetWindowRect	Method	method GetWindowRect	General	Normal
SetCurrentView	Method	method SetCurrentView	General	Normal
WindowHandle	Property Get	property WindowHandle	General	Normal

[ISmpPluginTab overview](#)

ISmpPluginTab members by frequency of use

Properties

Name	Type	HelpString	Category	Frequency of use
AddSmpPage	Method	method AddSmpPage	General	Normal
AddView	Method	method AddView	General	Normal
CreateFormView	Method	method CreateFormView	General	Normal
CreateView	Method	method CreateView	General	Normal
CreateWinFormsView	Method	method CreateWinFormsView	General	Normal
GetWindowRect	Method	method GetWindowRect	General	Normal
SetCurrentView	Method	method SetCurrentView	General	Normal
WindowHandle	Property Get	property WindowHandle	General	Normal

[ISmpPluginTab overview](#)

ICustomerEvents members by category

Properties

Name	Type	HelpString	Category	Frequency of use
OnCustomerAdd	Method	method OnCustomerAdd	General	Normal
OnCustomerDelete	Method	method OnCustomerDelete	General	Normal
OnCustomerEdit	Method	method OnCustomerEdit	General	Normal
OnShowCustomerDetails	Method	method OnShowCustomerDetails	General	Normal

[ICustomerEvents overview](#)

ICustomerEvents members by frequency of use

Properties

Name	Type	HelpString	Category	Frequency of use
OnCustomerDelete	Method	method OnCustomerDelete	General	Normal
OnCustomerEdit	Method	method OnCustomerEdit	General	Normal
OnShowCustomerDetails	Method	method OnShowCustomerDetails	General	Normal
OnCustomerAdd	Method	method OnCustomerAdd	General	Normal

[ICustomerEvents overview](#)

ISmpUser members by category

Properties

Name	Type	HelpString	Category	Frequency of use
CurrentLoginUser	Property Get	property CurrentLoginUser	General	Normal
InvokeChangePasswordDlg	Method	method InvokeChangePasswordDlg	General	Normal
InvokeLoginUserDlg	Method	method InvokeLoginUserDlg	General	Normal

[ISmpUser overview](#)

ISmpUser members by frequency of use

Properties

Name	Type	HelpString	Category	Frequency of use
CurrentLoginUser	Property Get	property CurrentLoginUser	General	Normal
InvokeChangePasswordDlg	Method	method InvokeChangePasswordDlg	General	Normal
InvokeLoginUserDlg	Method	method InvokeLoginUserDlg	General	Normal

[ISmpUser overview](#)

ISmpUserEvents members by category

Properties

Name	Type	HelpString	Category	Frequency of use
AddLoginUserPages	Method	method AddLoginUserPages	General	Normal
OnUserLogin	Method	method OnUserLogin	General	Normal
OnUserLogout	Method	method OnUserLogout	General	Normal

[ISmpUserEvents overview](#)

ISmpUserEvents members by frequency of use

Properties

Name	Type	HelpString	Category	Frequency of use
AddLoginUserPages	Method	method AddLoginUserPages	General	Normal
OnUserLogout	Method	method OnUserLogout	General	Normal
OnUserLogin	Method	method OnUserLogin	General	Normal

[ISmpUserEvents overview](#)

ISmpPluginTabEvents members by category

Properties

Name	Type	HelpString	Category	Frequency of use
OnSetCurView	Method	method OnSetCurView	General	Normal

[ISmpPluginTabEvents overview](#)

ISmpPluginTabEvents members by frequency of use

Properties

Name	Type	HelpString	Category	Frequency of use
OnSetCurView	Method	method OnSetCurView	General	Normal

[ISmpPluginTabEvents overview](#)

ISmpDialogExt members by category

Properties

Name	Type	HelpString	Category	Frequency of use
AddAboutBoxPages	Method	method AddAboutBoxPages	General	Normal
AddCustomerPages	Method	method AddCustomerPages	General	Normal
AddDeleteOldDataPages	Method	method AddDeleteOldDataPages	General	Normal
AddManageUserPages	Method	method AddManageUserPages	General	Normal
AddSetupPages	Method	method AddSetupPages	General	Normal
AddShopPages	Method	method AddShopPages	General	Normal
AddStockItemPages	Method	method AddStockItemPages	General	Normal
AddTransactionPages	Method	method AddTransactionPages	General	Normal

[ISmpDialogExt overview](#)

ISmpDialogExt members by frequency of use

Properties

Name	Type	HelpString	Category	Frequency of use
AddAboutBoxPages	Method	method AddAboutBoxPages	General	Normal
AddCustomerPages	Method	method AddCustomerPages	General	Normal
AddDeleteOldDataPages	Method	method AddDeleteOldDataPages	General	Normal
AddManageUserPages	Method	method AddManageUserPages	General	Normal
AddSetupPages	Method	method AddSetupPages	General	Normal
AddShopPages	Method	method AddShopPages	General	Normal
AddStockItemPages	Method	method AddStockItemPages	General	Normal
AddTransactionPages	Method	method AddTransactionPages	General	Normal

[ISmpDialogExt overview](#)

ISmpReceiptSettings members by category

Properties

Name	Type	HelpString	Category	Frequency of use
AlwaysPrintSalesReceipt	Property Get	property AlwaysPrintSalesReceipt	General	Normal
BypassPrintDlg	Property Get	property BypassPrintDlg	General	Normal
EnableDefaultReceiptPrinter	Property Get	property EnableDefaultReceiptPrinter	General	Normal
FooterText	Property Get	property FooterText	General	Normal
PhoneNumberAtFooter	Property Get	property PhoneNumberAtFooter	General	Normal
PrintFooterText	Property Get	property PrintFooterText	General	Normal
PrintReceiptsContinuously	Property Get	property PrintReceiptsContinuously	General	Normal
PrintShopNameAtHeader	Property Get	property PrintShopNameAtHeader	General	Normal
PrintTimeAtFooter	Property Get	property PrintTimeAtFooter	General	Normal
ReceiptPrinterName	Property Get	property ReceiptPrinterName	General	Normal
ReceiptSpacing	Property Get	property ReceiptSpacing	General	Normal

[ISmpReceiptSettings](#) overview

ISmpReceiptSettings members by frequency of use

Properties

Name	Type	HelpString	Category	Frequency of use
AlwaysPrintSalesReceipt	Property Get	property AlwaysPrintSalesReceipt	General	Normal
BypassPrintDlg	Property Get	property BypassPrintDlg	General	Normal
EnableDefaultReceiptPrinter	Property Get	property EnableDefaultReceiptPrinter	General	Normal
FooterText	Property Get	property FooterText	General	Normal
PhoneNumberAtFooter	Property Get	property PhoneNumberAtFooter	General	Normal
PrintFooterText	Property Get	property PrintFooterText	General	Normal
PrintReceiptsContinuously	Property Get	property PrintReceiptsContinuously	General	Normal
PrintShopNameAtHeader	Property Get	property PrintShopNameAtHeader	General	Normal
PrintTimeAtFooter	Property Get	property PrintTimeAtFooter	General	Normal
ReceiptPrinterName	Property Get	property ReceiptPrinterName	General	Normal
ReceiptSpacing	Property Get	property ReceiptSpacing	General	Normal

[ISmpReceiptSettings](#) overview

ISmpReportSettings members by category

Properties

Name	Type	HelpString	Category	Frequency of use
AllwaysPrintMembershipForm	Property Get	property AllwaysPrintMembershipForm	General	Normal
BypassPrintDlg	Property Get	property BypassPrintDlg	General	Normal
PrintPhNoAtFooter	Property Get	property PrintPhNoAtFooter	General	Normal
PrintShopLogo	Property Get	property PrintShopLogo	General	Normal
PrintShopNameAtHeader	Property Get	property PrintShopNameAtHeader	General	Normal
PrintTimeAtFooter	Property Get	property PrintTimeAtFooter	General	Normal

[ISmpReportSettings overview](#)

ISmpReportSettings members by frequency of use

Properties

Name	Type	HelpString	Category	Frequency of use
AllwaysPrintMembershipForm	Property Get	property AllwaysPrintMembershipForm	General	Normal
BypassPrintDlg	Property Get	property BypassPrintDlg	General	Normal
PrintPhNoAtFooter	Property Get	property PrintPhNoAtFooter	General	Normal
PrintShopLogo	Property Get	property PrintShopLogo	General	Normal
PrintShopNameAtHeader	Property Get	property PrintShopNameAtHeader	General	Normal
PrintTimeAtFooter	Property Get	property PrintTimeAtFooter	General	Normal

[ISmpReportSettings overview](#)

ISmpFrame members by category

Properties

Name	Type	HelpString	Category	Frequency of use
LeftToolbarHandle	Property Get	property LeftToolbarHandle	General	Normal
MainFrameHandle	Property Get	property MainFrameHandle	General	Normal
MainToolbarHandle	Property Get	property MainToolbarHandle	General	Normal
MenuHandle	Property Get	property MenuHandle	General	Normal
PluginToolbarCount	Property Get	property PluginToolbarCount	General	Normal
PluginToolbarHandle	Property Get	property PluginToolbarHandle	General	Normal
RightToolbarHandle	Property Get	property RightToolbarHandle	General	Normal
SetPaneStatusText	Method	method SetPaneStatusText	General	Normal
StatusbarHandle	Property Get	property StatusbarHandle	General	Normal

[ISmpFrame](#) overview

ISmpFrame members by frequency of use

Properties

Name	Type	HelpString	Category	Frequency of use
LeftToolbarHandle	Property Get	property LeftToolbarHandle	General	Normal
MainFrameHandle	Property Get	property MainFrameHandle	General	Normal
MainToolbarHandle	Property Get	property MainToolbarHandle	General	Normal
MenuHandle	Property Get	property MenuHandle	General	Normal
PluginToolbarCount	Property Get	property PluginToolbarCount	General	Normal
PluginToolbarHandle	Property Get	property PluginToolbarHandle	General	Normal
RightToolbarHandle	Property Get	property RightToolbarHandle	General	Normal
SetPaneStatusText	Method	method SetPaneStatusText	General	Normal
StatusbarHandle	Property Get	property StatusbarHandle	General	Normal

[ISmpFrame](#) overview

ISmpReportItemAttributes members by category

Properties

Name	Type	HelpString	Category	Frequency of use
BackgroundColor	Property Get/Let	property BackgroundColor	General	Normal
FooterBold	Property Get/Let	property FooterBold	General	Normal
FooterFont	Property Get/Let	property FooterFont	General	Normal
FooterFontSize	Property Get/Let	property FooterFontSize	General	Normal
FooterItalic	Property Get/Let	property FooterItalic	General	Normal
ForegroundColor	Property Get/Let	property ForegroundColor	General	Normal
GetMarginInfo	Method	method GetMarginInfo	General	Normal
HeadingBold	Property Get/Let	property HeadingBold	General	Normal
HeadingFont	Property Get/Let	property HeadingFont	General	Normal
HeadingFontSize	Property Get/Let	property HeadingFontSize	General	Normal
HeadingItalics	Property Get/Let	property HeadingItalics	General	Normal
ImageColumnPosition	Property Get/Let	property ImageColumnPosition	General	Normal
ImagePath	Property Get/Let	property ImagePath	General	Normal
ImageRowPosition	Property Get/Let	property ImageRowPosition	General	Normal
Item	Property Get/Let	property Item	General	Normal
ItemCount	Property Get/Let	property ItemCount	General	Normal
NormalBold	Property Get/Let	property NormalBold	General	Normal
NormalFont	Property Get/Let	property NormalFont	General	Normal
NormalFontSize	Property Get/Let	property NormalFontSize	General	Normal
NormalItalic	Property Get/Let	property NormalItalic	General	Normal
SetMarginInfo	Method	method SetMarginInfo	General	Normal
ShowHeading	Property Get/Let	property ShowHeading	General	Normal
ShowImage	Property Get/Let	property ShowImage	General	Normal

[ISmpReportItemAttributes overview](#)

ISmpReportItemAttributes members by frequency of use

Properties

Name	Type	HelpString	Category	Frequency of use
BackgroundColor	Property Get/Let	property BackgroundColor	General	Normal
FooterBold	Property Get/Let	property FooterBold	General	Normal
FooterFont	Property Get/Let	property FooterFont	General	Normal
FooterFontSize	Property Get/Let	property FooterFontSize	General	Normal
FooterItalic	Property Get/Let	property FooterItalic	General	Normal
ForegroundColor	Property Get/Let	property ForegroundColor	General	Normal
GetMarginInfo	Method	method GetMarginInfo	General	Normal
HeadingBold	Property Get/Let	property HeadingBold	General	Normal
HeadingFont	Property Get/Let	property HeadingFont	General	Normal
HeadingFontSize	Property Get/Let	property HeadingFontSize	General	Normal
HeadingItalics	Property Get/Let	property HeadingItalics	General	Normal
ImageColumnPosition	Property Get/Let	property ImageColumnPosition	General	Normal
ImagePath	Property Get/Let	property ImagePath	General	Normal
ImageRowPosition	Property Get/Let	property ImageRowPosition	General	Normal
Item	Property Get/Let	property Item	General	Normal
ItemCount	Property Get/Let	property ItemCount	General	Normal
NormalBold	Property Get/Let	property NormalBold	General	Normal
NormalFont	Property Get/Let	property NormalFont	General	Normal
NormalFontSize	Property Get/Let	property NormalFontSize	General	Normal
NormalItalic	Property Get/Let	property NormalItalic	General	Normal
SetMarginInfo	Method	method SetMarginInfo	General	Normal
ShowHeading	Property Get/Let	property ShowHeading	General	Normal
ShowImage	Property Get/Let	property ShowImage	General	Normal

[ISmpReportItemAttributes overview](#)

ISmpStock members by category

Properties

Name	Type	HelpString	Category	Frequency of use
InvokeAddNewStockDlg	Method	method InvokeAddNewStockDlg	General	Normal
InvokeCancelSalesDlg	Method	method InvokeCancelSalesDlg	General	Normal
InvokeCheckoutDlg	Method	method InvokeCheckoutDlg	General	Normal
InvokeEditStockDlg	Method	method InvokeEditStockDlg	General	Normal
InvokeModifyStockItemPriceDlg	Method	method InvokeModifyStockItemPriceDlg	General	Normal
InvokeStockRateSettingsDlg	Method	method InvokeStockRateSettingsDlg	General	Normal
ItemCount	Property Get	property ItemCount	General	Normal
ItemName	Property Get	property ItemName	General	Normal
StdSellingPricePerUnit	Property Get	property StdSellingPricePerUnit	General	Normal

[ISmpStock overview](#)

ISmpStock members by frequency of use

Properties

Name	Type	HelpString	Category	Frequency of use
InvokeAddNewStockDlg	Method	method InvokeAddNewStockDlg	General	Normal
InvokeCancelSalesDlg	Method	method InvokeCancelSalesDlg	General	Normal
InvokeCheckoutDlg	Method	method InvokeCheckoutDlg	General	Normal
InvokeEditStockDlg	Method	method InvokeEditStockDlg	General	Normal
InvokeModifyStockItemPriceDlg	Method	method InvokeModifyStockItemPriceDlg	General	Normal
InvokeStockRateSettingsDlg	Method	method InvokeStockRateSettingsDlg	General	Normal
ItemCount	Property Get	property ItemCount	General	Normal
ItemName	Property Get	property ItemName	General	Normal
StdSellingPricePerUnit	Property Get	property StdSellingPricePerUnit	General	Normal

[ISmpStock overview](#)

ISmpStockEvents members by category

Properties

Name	Type	HelpString	Category	Frequency of use
AddStockItemPages	Method	method AddStockItemPages	General	Normal
OnAddStockItem	Method	method OnAddStockItem	General	Normal
OnDeleteStockItem	Method	method OnDeleteStockItem	General	Normal
OnEditStockItem	Method	method OnEditStockItem	General	Normal

[ISmpStockEvents](#) overview

ISmpStockEvents members by frequency of use

Properties

Name	Type	HelpString	Category	Frequency of use
AddStockItemPages	Method	method AddStockItemPages	General	Normal
OnAddStockItem	Method	method OnAddStockItem	General	Normal
OnDeleteStockItem	Method	method OnDeleteStockItem	General	Normal
OnEditStockItem	Method	method OnEditStockItem	General	Normal

[ISmpStockEvents](#) overview

ISmpSetup members by category

Properties

Name	Type	HelpString	Category	Frequency of use
InvokeCategoryMasterDlg	Method	method InvokeCategoryMasterDlg	General	Normal
InvokeCurrencySettingsDlg	Method	method InvokeCurrencySettingsDlg	General	Normal
InvokeDefaultSettingsDlg	Method	method InvokeDefaultSettingsDlg	General	Normal
InvokeDefaultSettingsExtDlg	Method	method InvokeDefaultSettingsExtDlg	General	Normal
InvokeDeleteOldDataDlg	Method	method InvokeDeleteOldDataDlg	General	Normal
InvokeManageUsersDlg	Method	method InvokeManageUsersDlg	General	Normal
InvokeMethodOfPaymentDlg	Method	method InvokeMethodOfPaymentDlg	General	Normal
InvokeMiscItemMasterDlg	Method	method InvokeMiscItemMasterDlg	General	Normal
InvokeServiceMasterDlg	Method	method InvokeServiceMasterDlg	General	Normal
InvokeSetupWizard	Method	method InvokeSetupWizard	General	Normal
InvokeShopInfoDlg	Method	method InvokeShopInfoDlg	General	Normal
InvokeStockMasterDlg	Method	method InvokeStockMasterDlg	General	Normal

[ISmpSetup overview](#)

ISmpSetup members by frequency of use

Properties

Name	Type	HelpString	Category	Frequency of use
InvokeCategoryMasterDlg	Method	method InvokeCategoryMasterDlg	General	Normal
InvokeCurrencySettingsDlg	Method	method InvokeCurrencySettingsDlg	General	Normal
InvokeDefaultSettingsDlg	Method	method InvokeDefaultSettingsDlg	General	Normal
InvokeDefaultSettingsExtDlg	Method	method InvokeDefaultSettingsExtDlg	General	Normal
InvokeDeleteOldDataDlg	Method	method InvokeDeleteOldDataDlg	General	Normal
InvokeManageUsersDlg	Method	method InvokeManageUsersDlg	General	Normal
InvokeMethodOfPaymentDlg	Method	method InvokeMethodOfPaymentDlg	General	Normal
InvokeMiscItemMasterDlg	Method	method InvokeMiscItemMasterDlg	General	Normal
InvokeServiceMasterDlg	Method	method InvokeServiceMasterDlg	General	Normal
InvokeSetupWizard	Method	method InvokeSetupWizard	General	Normal
InvokeShopInfoDlg	Method	method InvokeShopInfoDlg	General	Normal
InvokeStockMasterDlg	Method	method InvokeStockMasterDlg	General	Normal

[ISmpSetup overview](#)

ISmpSetupEvents members by category

Properties

Name	Type	HelpString	Category	Frequency of use
OnPluginInvokeSetupWizard	Method	method OnPluginInvokeSetupWizard	General	Normal
OnSaveDefaultSettings	Method	method OnSaveDefaultSettings	General	Normal

[ISmpSetupEvents](#) overview

ISmpSetupEvents members by frequency of use

Properties

Name	Type	HelpString	Category	Frequency of use
OnPluginInvokeSetupWizard	Method	method OnPluginInvokeSetupWizard	General	Normal
OnSaveDefaultSettings	Method	method OnSaveDefaultSettings	General	Normal

[ISmpSetupEvents](#) overview

ISmpFileMenuOperations members by category

Properties

Name	Type	HelpString	Category	Frequency of use
InvokeBackupDataDlg	Method	method InvokeBackupDataDlg	General	Normal
InvokeChangePasswordDlg	Method	method InvokeChangePasswordDlg	General	Normal
InvokeExit	Method	method InvokeExit	General	Normal
InvokeExportReportDlg	Method	method InvokeExportReportDlg	General	Normal
InvokeLoginDlg	Method	method InvokeLoginDlg	General	Normal
InvokeLogout	Method	method InvokeLogout	General	Normal
InvokePrintDlg	Method	method InvokePrintDlg	General	Normal
InvokePrintOldReceiptDlg	Method	method InvokePrintOldReceiptDlg	General	Normal
InvokePrintPreviewDlg	Method	method InvokePrintPreviewDlg	General	Normal
InvokePrintSetupDlg	Method	method InvokePrintSetupDlg	General	Normal
InvokeRestoreDataDlg	Method	method InvokeRestoreDataDlg	General	Normal

[ISmpFileMenuOperations](#) overview

ISmpFileMenuOperations members by frequency of use

Properties

Name	Type	HelpString	Category	Frequency of use
InvokeBackupDataDlg	Method	method InvokeBackupDataDlg	General	Normal
InvokeChangePasswordDlg	Method	method InvokeChangePasswordDlg	General	Normal
InvokeExit	Method	method InvokeExit	General	Normal
InvokeExportReportDlg	Method	method InvokeExportReportDlg	General	Normal
InvokeLoginDlg	Method	method InvokeLoginDlg	General	Normal
InvokeLogout	Method	method InvokeLogout	General	Normal
InvokePrintDlg	Method	method InvokePrintDlg	General	Normal
InvokePrintOldReceiptDlg	Method	method InvokePrintOldReceiptDlg	General	Normal
InvokePrintPreviewDlg	Method	method InvokePrintPreviewDlg	General	Normal
InvokePrintSetupDlg	Method	method InvokePrintSetupDlg	General	Normal
InvokeRestoreDataDlg	Method	method InvokeRestoreDataDlg	General	Normal

[ISmpFileMenuOperations](#) overview

ISmpHelp members by category

Properties

Name	Type	HelpString	Category	Frequency of use
HelpFilePath	Property Get	property HelpFilePath	General	Normal
InvokeAboutBoxDlg	Method	method InvokeAboutBoxDlg	General	Normal
InvokeHelpTopics	Method	method InvokeHelpTopics	General	Normal
InvokeMenuShortcutKeyDlg	Method	method InvokeMenuShortcutKeyDlg	General	Normal
InvokeRegisterDlg	Method	method InvokeRegisterDlg	General	Normal
InvokeTipOfTheDayDlg	Method	method InvokeTipOfTheDayDlg	General	Normal

[ISmpHelp overview](#)

ISmpHelp members by frequency of use

Properties

Name	Type	HelpString	Category	Frequency of use
HelpFilePath	Property Get	property HelpFilePath	General	Normal
InvokeAboutBoxDlg	Method	method InvokeAboutBoxDlg	General	Normal
InvokeHelpTopics	Method	method InvokeHelpTopics	General	Normal
InvokeMenuShortcutKeyDlg	Method	method InvokeMenuShortcutKeyDlg	General	Normal
InvokeRegisterDlg	Method	method InvokeRegisterDlg	General	Normal
InvokeTipOfTheDayDlg	Method	method InvokeTipOfTheDayDlg	General	Normal

[ISmpHelp overview](#)

ISmpReportMenu members by category

Properties

Name	Type	HelpString	Category	Frequency of use
InvokeAnualAccountDlg	Method	method InvokeAnualAccountDlg	General	Normal
InvokeAnualStatisticsDlg	Method	method InvokeAnualStatisticsDlg	General	Normal
InvokeCanceledSalesDlg	Method	method InvokeCanceledSalesDlg	General	Normal
InvokeCanceledTransactionsDlg	Method	method InvokeCanceledTransactionsDlg	General	Normal
InvokeCustomerBalanceAmountDlg	Method	method InvokeCustomerBalanceAmountDlg	General	Normal
InvokeCustomerInactiveDlg	Method	method InvokeCustomerInactiveDlg	General	Normal
InvokeCustomerListDlg	Method	method InvokeCustomerListDlg	General	Normal
InvokeCustomerMostActiveDlg	Method	method InvokeCustomerMostActiveDlg	General	Normal
InvokeCustomerPaymentDetailsdlg	Method	method InvokeCustomerPaymentDetailsdlg	General	Normal
InvokeCustomerRefundDetailsDlg	Method	method InvokeCustomerRefundDetailsDlg	General	Normal
InvokeCustomerSalesDetailsDlg	Method	method InvokeCustomerSalesDetailsDlg	General	Normal
InvokeCustomerTransactionDetailsDlg	Method	method InvokeCustomerTransactionDetailsDlg	General	Normal
InvokeDailyAccountDlg	Method	method InvokeDailyAccountDlg	General	Normal
InvokeDailySummaryDlg	Method	method InvokeDailySummaryDlg	General	Normal
InvokeDiscountSalesDlg	Method	method InvokeDiscountSalesDlg	General	Normal
InvokeMiscTransactionListDlg	Method	method InvokeMiscTransactionListDlg	General	Normal
InvokeMonthlyAccountDlg	Method	method InvokeMonthlyAccountDlg	General	Normal
InvokeMonthlyStatisticsDlg	Method	method InvokeMonthlyStatisticsDlg	General	Normal
InvokeReorderListDlg	Method	method InvokeReorderListDlg	General	Normal
InvokeRollbackDlg	Method	method InvokeRollbackDlg	General	Normal
InvokeSalesListDlg	Method	method InvokeSalesListDlg	General	Normal
InvokeServiceDeliveredDlg	Method	method InvokeServiceDeliveredDlg	General	Normal
InvokeServiceListDlg	Method	method InvokeServiceListDlg	General	Normal
InvokeSpecifiedPeriodAccountDlg	Method	method InvokeSpecifiedPeriodAccountDlg	General	Normal
InvokeStokeListDlg	Method	method InvokeStokeListDlg	General	Normal
InvokeTransactionListDlg	Method	method InvokeTransactionListDlg	General	Normal

ISmpReportMenu overview

ISmpReportMenu members by frequency of use

Properties

Name	Type	HelpString	Category	Frequency of use
InvokeAnualAccountDlg	Method	method InvokeAnualAccountDlg	General	Normal
InvokeAnualStatisticsDlg	Method	method InvokeAnualStatisticsDlg	General	Normal
InvokeCanceledSalesDlg	Method	method InvokeCanceledSalesDlg	General	Normal
InvokeCanceledTransactionsDlg	Method	method InvokeCanceledTransactionsDlg	General	Normal
InvokeCustomerBalanceAmountDlg	Method	method InvokeCustomerBalanceAmountDlg	General	Normal
InvokeCustomerInactiveDlg	Method	method InvokeCustomerInactiveDlg	General	Normal
InvokeCustomerListDlg	Method	method InvokeCustomerListDlg	General	Normal
InvokeCustomerMostActiveDlg	Method	method InvokeCustomerMostActiveDlg	General	Normal
InvokeCustomerPaymentDetailsdlg	Method	method InvokeCustomerPaymentDetailsdlg	General	Normal
InvokeCustomerRefundDetailsDlg	Method	method InvokeCustomerRefundDetailsDlg	General	Normal
InvokeCustomerSalesDetailsDlg	Method	method InvokeCustomerSalesDetailsDlg	General	Normal
InvokeCustomerTransactionDetailsDlg	Method	method InvokeCustomerTransactionDetailsDlg	General	Normal
InvokeDailyAccountDlg	Method	method InvokeDailyAccountDlg	General	Normal
InvokeDailySummaryDlg	Method	method InvokeDailySummaryDlg	General	Normal
InvokeDiscountSalesDlg	Method	method InvokeDiscountSalesDlg	General	Normal
InvokeMiscTransactionListDlg	Method	method InvokeMiscTransactionListDlg	General	Normal
InvokeMonthlyAccountDlg	Method	method InvokeMonthlyAccountDlg	General	Normal
InvokeMonthlyStatisticsDlg	Method	method InvokeMonthlyStatisticsDlg	General	Normal
InvokeReorderListDlg	Method	method InvokeReorderListDlg	General	Normal
InvokeRollbackDlg	Method	method InvokeRollbackDlg	General	Normal
InvokeSalesListDlg	Method	method InvokeSalesListDlg	General	Normal
InvokeServiceDeliveredDlg	Method	method InvokeServiceDeliveredDlg	General	Normal
InvokeServiceListDlg	Method	method InvokeServiceListDlg	General	Normal
InvokeSpecifiedPeriodAccountDlg	Method	method InvokeSpecifiedPeriodAccountDlg	General	Normal
InvokeStokeListDlg	Method	method InvokeStokeListDlg	General	Normal
InvokeTransactionListDlg	Method	method InvokeTransactionListDlg	General	Normal

ISmpReportMenu overview

IISmpReportMenuEvents members by category

Properties

Name	Type	HelpString	Category	Frequency of use
OnAnualStatisticsReport	Method	method OnAnualStatisticsReport	General	Normal
OnMonthlyStatisticsReport	Method	method OnMonthlyStatisticsReport	General	Normal

[IISmpReportMenuEvents](#) overview

IISmpReportMenuEvents members by frequency of use

Properties

Name	Type	HelpString	Category	Frequency of use
OnAnualStatisticsReport	Method	method OnAnualStatisticsReport	General	Normal
OnMonthlyStatisticsReport	Method	method OnMonthlyStatisticsReport	General	Normal

[IISmpReportMenuEvents](#) overview

ISmpSettingsEx members by category

Properties

Name	Type	HelpString	Category	Frequency of use
ReloadAllApplicationSettings	Method	method ReloadAllApplicationSettings	General	Normal
ReloadAllDefaultSettings	Method	method ReloadAllDefaultSettings	General	Normal
ReloadAllLocalSettings	Method	method ReloadAllLocalSettings	General	Normal

[ISmpSettingsEx overview](#)

ISmpSettingsEx members by frequency of use

Properties

Name	Type	HelpString	Category	Frequency of use
ReloadAllApplicationSettings	Method	method ReloadAllApplicationSettings	General	Normal
ReloadAllDefaultSettings	Method	method ReloadAllDefaultSettings	General	Normal
ReloadAllLocalSettings	Method	method ReloadAllLocalSettings	General	Normal

[ISmpSettingsEx overview](#)